

# **JacORB 3.6 Programming Guide**

The JacORB Team

February 16, 2015

**Contributors in alphabetical order:**

Alexander Bykov  
Alphonse Bendt  
Gerald Brose  
Nick Cross  
Phil Mesnier  
Quynh Nguyen  
Nicolas Noffke  
Steve Osselton  
Simon McQueen  
Francisco Reverbel  
David Robison  
André Spiegel

# Contents

<b>1</b>	<b>Introduction</b>	<b>9</b>
1.1	A Brief CORBA introduction	9
1.2	Project History	10
1.3	Support	11
1.4	Contributing — Donations	11
1.5	Contributing — Development	11
1.6	Feedback, Bug reports	12
<b>2</b>	<b>Installing JacORB</b>	<b>13</b>
2.1	Downloading JacORB	13
2.2	Installation	13
2.2.1	Requirements	13
2.2.2	Procedure	13
2.2.3	Libraries	13
2.2.4	Dependencies	14
2.2.5	Building JacORB	14
2.3	Versioning	15
<b>3</b>	<b>Configuration</b>	<b>17</b>
3.1	Configuration Mechanism	17
3.1.1	Properties files	17
3.1.2	Command-line properties	19
3.1.3	Arguments to ORB.init()	20
3.2	Configuration Options	20
3.2.1	Initial references	20
3.2.2	Acceptor Exception Event Plugin	21
3.2.3	Codesets	22
3.2.4	Compacting Typecodes	22
3.2.5	CORBA Object Keys	23
3.2.6	IORMutator	25
3.2.7	Listen Endpoints	25
3.2.8	Loading Classes and Resources	27
3.2.9	Logging	27
3.2.10	Network and Sockets	30
3.2.11	Network Event Logging	34

3.2.12	NIO Support	35
3.2.13	Using Object.release	36
3.3	Configuration Properties	36
3.3.1	ORB Configuration	36
3.3.2	Network Configuration	44
3.3.3	Logging Configuration	46
3.3.4	POA Configuration	47
3.3.5	Implementation Repository Configuration	48
3.3.6	Security Configuration	49
3.3.7	Name Service Configuration	53
<b>4</b>	<b>Getting Started</b>	<b>55</b>
4.1	JacORB development: an overview	55
4.2	IDL specifications	55
4.3	Generating Java classes	56
4.4	Implementing the interface	57
4.4.1	The Tie Approach	59
4.5	Writing the Server	60
4.6	Writing a client	61
4.7	Running the Example Application	63
<b>5</b>	<b>Maven</b>	<b>65</b>
5.1	Maven Central	65
5.2	Maven Demo	65
<b>6</b>	<b>The JacORB Name Service</b>	<b>67</b>
6.1	Running the Name Server	67
6.2	Accessing the Name Service	68
6.3	Constructing Hierarchies of Name Spaces	69
6.4	NameManager — A simple GUI front-end to the Naming Service	70
<b>7</b>	<b>The server side: POA, Threads</b>	<b>71</b>
7.1	POA	71
7.2	Threads	72
<b>8</b>	<b>Implementation Repository</b>	<b>73</b>
8.1	Overview	73
8.2	Using the JacORB Implementation Repository	74
8.3	Server migration	76
8.4	A Note About Security	77
<b>9</b>	<b>TAO Implementation Repository</b>	<b>79</b>
9.1	Introduction	79
9.2	The Operation of the TAO ImR	80

---

9.3	Using the TAO Implementation Repository	80
9.3.1	Server Requirements	81
9.3.2	Client Requirements	81
9.3.3	Environment Variables	82
9.3.4	Initiate The TAO ImR Locator <code>tao_imr_locator</code>	82
9.3.5	Initiate The TAO ImR Activator	83
9.3.6	Register the JacORB server	83
9.3.7	Server Start-up	85
9.3.8	Initiate the JacORB client	86
9.4	Repository Persistence	87
9.5	TAO ImR Utility	88
9.5.1	Command Line Options	88
9.6	<code>tao_imr_locator</code>	91
9.6.1	Command Line Options	91
9.6.2	Examples	93
9.7	<code>tao_imr_activator</code>	94
9.7.1	Command Line Options	95
9.7.2	Examples	96
<b>10</b>	<b>Interface Repository</b>	<b>97</b>
10.1	Type Information in the IR	97
10.2	Repository Design	98
10.3	Using the IR	99
10.4	Interaction between <code>#pragma prefix</code> and <code>-i2jpackage</code>	100
<b>11</b>	<b>Dynamic Management of Any Values</b>	<b>103</b>
11.1	Overview	103
11.2	Interfaces	103
11.3	Usage Constraints	104
11.4	Creating a DynAny Object	104
11.5	Accessing the Value of a DynAny Object	106
11.6	Traversing the Value of a DynAny Object	106
11.7	Constructed Types	108
11.7.1	DynFixed	108
11.7.2	DynEnum	108
11.7.3	DynStruct	108
11.7.4	DynUnion	108
11.7.5	DynSequence	109
11.7.6	DynArray	109
11.8	Converting between Any and DynAny Objects	109
11.9	Further Examples	110

<b>12 Objects By Value</b>	<b>111</b>
12.1 Example	111
12.2 Factories	113
<b>13 IIOP over SSL</b>	<b>115</b>
13.1 Key stores	115
13.1.1 Setting up a JSSE key store	115
13.1.2 Step-By-Step certificate creation	117
13.2 Configuring SSL properties	117
13.2.1 Protocols	119
13.2.2 Client side and server side configuration	119
13.3 SecureRandom Plugin System	122
13.4 Security and corbaloc	122
<b>14 MIOP</b>	<b>125</b>
14.1 Enabling the MIOP Transport	125
14.2 Configuring the MIOP Transport	125
14.3 MIOP Example	126
14.3.1 Two way requests and MIOP	127
<b>15 BiDirectional GIOP</b>	<b>129</b>
15.1 Setting up Bidirectional GIOP	129
15.1.1 Setting the ORBInitializer property	129
15.1.2 Creating the BiDir Policy	129
15.2 Verifying that BiDirectional GIOP is used	130
15.3 TAO interoperability	130
<b>16 Portable Interceptors</b>	<b>131</b>
16.1 Interceptor ForwardRequest Exceptions	131
16.2 Public API	132
<b>17 Asynchronous Method Invocation</b>	<b>135</b>
<b>18 Quality of Service</b>	<b>137</b>
18.1 Sync Scope	138
18.2 Timing Policies	139
<b>19 Connection Management and Connection Timeouts</b>	<b>143</b>
19.1 Timeouts	143
19.2 Connection Management	143
19.2.1 Basics and Design	144
19.2.2 Configuration	145
19.2.3 Limitations	146

---

<b>20 Extensible Transport Framework</b>	<b>147</b>
20.1 Implementing a new Transport	147
20.2 Configuring Transport Usage	148
20.3 Selecting Specific Profiles Using RT Policies	149
<b>21 Security Attribute Service</b>	<b>151</b>
21.1 Overview	151
21.2 GSSUP Example	152
21.2.1 GSSUP IDL Example	152
21.2.2 GSSUP Client Example	152
21.2.3 GSSUP Target Example	153
21.3 Kerberos Example	155
21.3.1 Kerberos IDL Example	155
21.3.2 Kerberos Client Example	155
21.3.3 Kerberos Target Example	157
<b>22 The JacORB Notification Service</b>	<b>161</b>
22.1 Unsupported Features	161
22.2 Installation	161
22.3 Running the Notification Service	161
22.3.1 Running as a NT Service or an UNIX Daemon	162
22.3.2 Running as a JBoss Service	163
22.4 Accessing the Notification Service	164
22.5 Configuration	164
22.5.1 Setting up Bidirectional GIOP	167
22.6 Monitoring the Notification Service	167
22.6.1 Download MX4J	167
22.6.2 Edit Java Service Wrapper configuration	168
22.6.3 Start the Service	168
22.6.4 Connecting to the management console	168
22.7 Extending the JacORB Notification Service	168
22.7.1 Adding custom Filters	168
<b>23 Using Java management Extentions (JMX)</b>	<b>171</b>
23.1 MX4J and JMX over IIOP	171
<b>24 Transport Current</b>	<b>173</b>
24.1 Scope and Context	173
24.2 Programmer's Reference	173
24.3 User's Guide	176
24.3.1 Configuration, Bootstrap, Initialization and Operation	176

<b>25 JacORB Utilities</b>	<b>179</b>
25.1 idl . . . . .	179
25.2 ns . . . . .	185
25.3 nmg . . . . .	185
25.4 lsns . . . . .	186
25.5 dior . . . . .	186
25.6 pingo . . . . .	187
25.7 ir . . . . .	187
25.8 qir . . . . .	187
25.9 ks . . . . .	187
25.10fixior . . . . .	188
<b>26 JacORB Threads</b>	<b>189</b>
<b>27 Classpath and Classloaders</b>	<b>195</b>
27.1 Running applications . . . . .	195
27.1.1 ORBSingleton . . . . .	195
27.2 Interaction with Classloaders . . . . .	196
<b>28 Appendix</b>	<b>197</b>
28.1 API Documentation . . . . .	197
28.2 OMG ORB Constants . . . . .	197

## Document Formatting

- Command lines are formatted using \$ <command> as per Unix format.



# 1 Introduction

This document gives an introduction to programming distributed applications with JacORB, a free Java object request broker. JacORB comes with full source code, a couple of CORBA Object Service implementations, and a number of example programs.

The JacORB version described in this document is JacORB 3.6. The release notes may be found in `<install>/doc/REL_NOTES`. The current implementation attempts to conform to the CORBA 3.1 specification.

## 1.1 A Brief CORBA introduction

CORBA models distributed resources as objects that provide a well-defined interface. CORBA lets you invoke services through remote invocations (RPCs). Since the transfer syntax for sending messages to objects is strictly defined, it is possible to exchange requests and replies between processes running program written in arbitrary programming languages and hosted on arbitrary hardware and operating systems. Target addresses are represented as Interoperable Object References (IORs), which contain transport addresses as well as identifiers needed to dispatch incoming messages to implementations.

Interfaces to remote objects are described declaratively in an programming language-independent Interface Definition Language (IDL), which can be used to automatically generate language-specific stub code.

It is important to stress that:

- CORBA objects as seen by clients are abstract entities. Their behavior is implemented by artifacts in potentially arbitrary, even non-OO languages. These artifacts are called servants in CORBA terminology. A servant is not the same as the object. Servants require an ORB implementation to maintain the relationship to objects and to mediate requests and responses.
- CORBA objects achieve location transparency, i.e., clients need not be (and generally are not) aware of the actual target hosts where servants reside. However, complete distribution transparency is not achieved in the sense that clients would not notice a difference between a local function call and a remote CORBA invocation. This is due to factors such as increased latency, network error conditions, and CORBA-specific initialization code in

applications, and data type mappings.

Please see [?, ?, ?] for more information and additional details, and [?] for advanced issues.

## 1.2 Project History

JacORB originated in 1995 (was it 1996?) in the CS department at Freie Universität Berlin (FUB). It evolved from a small Java RPC library and a stub compiler that would process Java interfaces. This predecessor was written — most for fun and out of curiosity — by Boris Bokowski and Gerald Brose because at that time no Java RMI was available. The two of us then realized how close the Java interface syntax was to CORBA IDL, so we wrote an IDL grammar for our parser generator and moved to GIOP and IIOP as the transport protocol. It was shortly before Christmas 1996 when the first interoperable GIOP request was sent from a JacORB client to an IONA Orbix server. For a long time, JacORB was the only free (in the GNU sense) Java/CORBA implementation available, and it soon enjoyed widespread interest, at first mostly in academic projects, but commercial use followed soon after.

For a while, Gerald developed JacORB as a one-man-project until a few student projects and master theses started adding to it, most notably Reimo Tiedemann's POA implementation, and Nicolas Noffke's Implementation Repository and Portable Interceptor implementations. Other early contributors were Sebastian Müller, who wrote the Appligator, and Herbert Kiefer, who added a policy domain service. The Appligator and the policy domain service are no longer part of the JacORB distribution.

A more recent addition is Alphonse Bendt's implementation of the CORBA Notification Services as part of his master's theses. Substantial additions to the JacORB core were made by André Spiegel, who contributed OBV and AMI implementations. Other substantial contributions to JacORB have been added over time by the team at PrismTech UK (Steve Osselton, Nick Cross, Simon McQueen, Jason Courage) (<http://www.prismtech.com>), Simon McQueen of MicroFocus (), Nick Cross of Red Hat (<http://www.redhat.com>) and Phil Mesnier of OCI (<http://www.ociweb.com>). Other active contributors are Francisco Reverbel of the Red Hat JBoss team (RMI/IIOP) (<http://www.redhat.com>) and David Robison, who contributed CSIv2.

JacORB continues to be used for research at FUB, especially in the field of distributed object security. A number of people from the original research group have now left FUB; Gerald is with Projektron BCS (<http://www.projektron.de>), Reimo is with CoreMedia (<http://www.coremedia.com>), Nico and Alphonse worked at Xtradyne (<http://www.xtradyne.com>) (now part of PrismTech (<http://www.prismtech.com>)) and André Spiegel is now a free-lance developer and consultant (<http://www.free-software-consulting.com>).

Due to the limited number of developers, the philosophy around the development has never been to achieve feature-completeness beyond the core 90%, but standards compliance and quality. (e.g., JacORB 2.0 does not come with a PolicyManager). Brand-new and less widely-used features had to wait until the specification had reached a minimum maturity — or until someone

offered project funding.

## 1.3 Support

The JacORB core team and the user community together provide best effort support over our mailing lists.

To enquire about commercial support, please refer to <http://www.jacorb.org/support.html>.

## 1.4 Contributing — Donations

In essence, the early development years were entirely funded by public research. JacORB did receive some sponsoring over the years, but not as much as would have been desirable. A few development tasks that would otherwise not have been possible could be payed for, but more would have been possible — and still is.

If you feel that returning some of the value created by the use of Open Source software in your company is a wise investment in the future of that the software (maintenance, quality improvements, further development) in the future, then you should contact us about donations.

Buying hardware and sending it to us is one option. It is also possible to directly donate money to the JacORB project itself. If approval for outright donations is difficult to obtain at your company, we can send you an invoice for, e.g., CORBA consulting. For more information, contact the current maintainer listed at <http://www.jacorb.org/authors.html>

## 1.5 Contributing — Development

If you want to contribute to the development of the software directly, you should do the following:

- download JacORB and run the software to gain some first-hand expertise first
- read this document and other sources of CORBA documentation, such as [?], and the OMG's set of specifications (CORBA spec., IDL/Java language mapping)
- start reading the code
- subscribe to the `jacorb-developer` mailing list to share your expertise
- contact us to get subscribed to the core team's mailing list and send pull requests to the GIT repository.
- read the coding guide lines
- contribute code and test cases

## 1.6 Feedback, Bug reports

For limitations, known bugs and bug reporting, please use our Bugzilla bug tracking system available at <http://www.jacorb.org/bugzilla>. Please send problems as well as criticism and experience reports to our developer mailing list available from <http://www.jacorb.org/contact.html>.

## 2 Installing JacORB

In this chapter we explain how to obtain and install JacORB, and give an overview of the package contents.

### 2.1 Downloading JacORB

JacORB can be downloaded as a source or binary distribution in a g-zipped tar-archive or zip-archive format from the JacORB home page at <http://www.jacorb.org>. It is also available from Maven Central (See 5). To install JacORB, first unzip and untar (or simply unzip) the archive somewhere. This will result in a new directory `jacorb-3.6`.

### 2.2 Installation

#### 2.2.1 Requirements

JacORB requires JDK 1.6 or above properly installed on your machine. To build JacORB and run the tests Maven (<https://maven.apache.org>) is required (tested with 3.0.x).

#### 2.2.2 Procedure

- No further steps are required if using the binary download of JacORB.
- To configure a `jacorb.properties` file (using the `etc/jacorb-properties.template`) see 3.
- If using a source download, to rebuild JacORB completely see 2.2.5.

For SSL, you need an implementation of the SSL protocol. We currently support Oracle's JSSE Reference implementation included in the JDK.

#### 2.2.3 Libraries

Once JacORB is installed, the `bin` directory should contain the scripts used to assist in running JacORB applications (see 4.7 and 27.1). The `lib` directory contains the JacORB libraries and

third party libraries required by the ORB and services (See below). JacORB libraries have been split as follows:

- `jacorb.jar` - containing the ORB, IMR, IR and NamingService
- `jacorb-omgapi.jar` - containing the core OMG API stubs.
- `jacorb-services.jar` - containing all other services (e.g. Notification, DDS, Collection etc).
- `idl.jar` - containing the IDL compiler.

## 2.2.4 Dependencies

JacORB depends upon the following third party software

- Simple Logging Facade For Java (SLF4J Version 1.7.6)

Note that the services may depend upon further third party libraries.

## 2.2.5 Building JacORB

JacORB may be built via Maven using standard commands (i.e. `mvn clean install`). Note that the install phase must be executed so subsequent module builds find the results of preceding modules. The project may be imported into Eclipse or IntelliJ using standard import commands.

### Importing into Eclipse

- Prior to importing it is recommended to build JacORB first (e.g. `mvn install -DskipTests=true`)
- The JacORB Core and Regression Test module utilises Endorsed Directories to build within the `maven-compiler-plugin`. In Eclipse, the JBoss Tools Endorsed Libraries Plugin must be installed for this to work.
- It is possible further m2e connectors (e.g. `build-helper`) must also be installed.

### Building JacORB Demos (Optional)

To build the JacORB demos within the demo directory Maven pom file(s) have been supplied. Run "mvn install" in the respective demo directories.

### Building JBoss Service for the Notification Service (Optional)

In order to build the JBoss service (jboss-cosnotification.sar in the lib directory), the paths to JBOSS\_HOME for the [JBoss Application Server](#) and MX4J\_HOME for the [MX4J implementation](#) of the Java Management Extensions (JMX) have to be specified for the ant build process. There are two possible alternatives for this task.

- Set the paths in the environment variables named JBOSS\_HOME and MX4J\_HOME respectively.
- Call ant with the additional parameters `-Djboss.home=<path-to-jboss-installation>`  
`-Dmx4j.home=<path-to-mx4j-installation>`

## 2.3 Versioning

There are a variety of ways of determining the version of JacORB that is being used.

- The configuration option `jacorb.orb.print_version` may be used to output the version to the logfile when JacORB is running
- The IDL compiler '-v' will output the version of the compiler/JacORB.
- The command `jaco org.jacorb.util.Version` may be run to output the current version and build date.
- The command `jaco org.jacorb.util.Diagnostic` may be run to output useful environmental information as well as the JacORB version.





# 3 Configuration

This chapter explains the general mechanism for configuring JacORB and lists all configuration properties. Note that as JacORB's configuration has been updated it is recommended to use the new `jacorb.properties` file supplied with this version.

## 3.1 Configuration Mechanism

JacORB has a number of configuration options which can be set as Java properties. There are three options for setting properties:

- in properties files
- as command line properties, and
- as properties passed as arguments to `ORB.init()` in the code of your applications.

In the case of a single JVM with multiple ORB instances, it may be required to either share configuration options between ORBs, or to separate the individual configurations from each other. We explain how properties can be set for sharing or for individual ORB instances.

### 3.1.1 Properties files

JacORB looks for a few standard properties files, a common file called `orb.properties`, and an ORB-specific file called `<orbid>.properties`, where `<orbid>` is the name of an ORB instance that was explicitly configured. Moreover, JacORB can load custom properties files from arbitrary locations. We explain each of these files in turn.

#### The common properties file

The reason for having a common properties file is that a single JacORB installation may be shared by a number of users with a set of common default properties. These may be refined by users in their own properties files but still provide reasonable defaults for the environment. Note that it is not required to have a common properties file as all configuration options can also be set in other files, on the commandline or in the code.

JacORB looks for the common properties file `orb.properties` in the following places:

1. in the `lib` directory of the JDK installation. (The JDK's home directory denoted by the system property `"java.home"`).
2. in the user home directory. (This is denoted by the system property `"user.home"`. On Windows, this is `c:\documents\username`, on Unixes it's `~user`. If in doubt where your home directory is, write a small Java program that prints out this property.
3. on the class path.

The common properties file is searched in the order presented above, so you may actually be loading multiple files of this name. If a properties file is found it is loaded, and any property values defined in this file will override values of the same property that were loaded earlier. Loading properties files from the classpath is useful when distributing applications packaged in JAR files.

### The ORB properties file

Having ORB-specific properties files is necessary when multiple ORB instances live in the same process, but need to have separate configurations, e.g., some ORBs use SSL and others don't, or some ORBs need to listen on separate but predefined ports. To let colocated ORBs use and retrieve separate configurations, JacORB provides a lookup mechanisms based on a specific property, the `ORBid` property. The default value for the `ORBid` is `jacorb`, ie. if the `ORBid` is not explicitly set anywhere, it defaults to `jacorb`. Note that this `ORBid` is reserved, ie., you cannot explicitly set your `ORBid` to this value. To use different configurations for different ORBs, you simply pass different `ORBid` values to your ORBs.

JacORB looks for ORB properties files in these places:

1. `jacorb.config.dir/etc/orbid.properties.`, if that exists, or
2. `jacorb.home/etc/orbid.properties.`, or
3. the current directory (`'./orbid.properties.'`)
4. on the class path.

The `jacorb.config.dir` and `jacorb.home` properties must be set for JacORB to be able to use a preconfigured configuration directory. The `jacorb.home` property defaults to `''`, if unset. Setting these properties can be done in the `orb.properties` file, or by passing a property in on the commandline, like this:

```
$ jaco -Djacorb.config.dir=c:/ -DORBid=example test.Example
```

This commandline causes JacORB to look for a file called `example.properties` in `c:/etc`. If the `-DORBid=example` had been ommitted, the name of the ORB properties file that JacORB would try to load would have been `jacorb.properties`, because that is the default value for the `ORBid`. A good starting point is to have a common properties file that

sets the `jacorb.config.dir` property, and then have put a `jacorb.properties` file in that directory.

Note, however, that the added flexibility of using multiple configuration files may lead to individual properties defined in multiple files. You must know the order in which your configuration files are loaded to avoid confusion over property settings not having the expected effect!

### Custom properties files

In addition to the standard JacORB properties files, a custom properties file can be loaded by passing the name of that properties files the `custom.props` property to JacORB. This can be handy for application-specific settings that you want to distribute with your code.

The value of this property is the path to a properties file, which contains the properties you want to load. As an example, imagine that you usually use plain TCP/IP connections, but in some cases want to use SSL (see section 13). The different ways of achieving this are

- Use just one properties file, but you will have to edit that file if you want to switch between SSL and plaintext connections.
- Use commandline properties exclusively (cf. below), which may lead to very long commands
- Use a command property file for all applications and different custom properties files for each application.

For example, you could start a JacORB program like this:

```
$ jaco -Dcustom.props=c:/tmp/ns.props org.jacorb.naming.NameServer
```

In addition to loading any standard properties files found in the places listed above, JacORB will now also load configuration properties from the file `c:/tmp/ns.props`, but this last file will be loaded after the default properties files and its values will thus take precedence over earlier settings.

### 3.1.2 Command-line properties

In the same way as the `custom.props` property in the example above, arbitrary other Java properties can be passed to JacORB programs using the `-D<prop name>=<prop value>` command line syntax for the `java` interpreter, but can be used in the same way with the `jaco` script. Note that the properties must precede the class name on the command line. For example to override the ORB initial references for NameService the following may be used:

```
jaco -DORBInitRef.NameService=file:///usr/users/...../NameService.ior
      Server
```

The ORB configuration mechanism will give configuration properties passed in this way precedence over property values found in configuration files.

Anything that follows after the class name is interpreted (by `java`) as a command line argument to the class and will be visible in the `args` parameter of the classes main method. For example

```
jaco Server
  -ORBInitRef.NameService=file:///usr/users/..../NameService.ior
```

### 3.1.3 Arguments to `ORB.init()`

For more application-specific properties, you can pass a `java.util.Properties` object to `ORB.init()` during application initialization. Properties set this way will override properties set by a properties file. The following code snippet demonstrates how to pass in a `Properties` object (`args` is the `String` array containing command line arguments):

```
java.util.Properties props = new java.util.Properties();
props.setProperty("jacorb.implname", "StandardNS");
org.omg.CORBA.ORB orb = org.omg.CORBA.ORB.init(args, props);
```

### ORBSingleton

A user does not have to use a properties file just passing arguments to `ORB.init(...)` to configure the ORB. In order to allow the singleton ORB to be configured JacORB will implicitly pass all `ORB.init(...)` arguments to the singleton for configuration purposes.

## 3.2 Configuration Options

We are now ready to have a look at the most basic JacORB configuration properties. As a starting point, you should look at the file `/etc/jacorb.properties.template`, which you can adapt to your own needs (e.g. renaming to `jacorb.properties` or `orb.properties` as required).

### 3.2.1 Initial references

Initial references are object references that are available to CORBA application through the bootstrap `orb.resolve_initial_service()` API call. This call takes a string argument as the name of an initial reference and returns a CORBA object reference, e.g., to the initial name service.

```
#####
#
#   Initial references configuration   #
```

```

#                                     #
#####

#
# URLs where IORs are stored (used in orb.resolve_initial_service())
# DO EDIT these! (Only those that you are planning to use,
# of course ;-).
#
# The ORBInitRef references are created on ORB startup time. In the
# cases of the services themselves, this may lead to exceptions being
# displayed (because the services aren't up yet). These exceptions
# are handled properly and cause no harm!

#ORBInitRef.NameService=corbaloc::160.45.110.41:38693/StandardNS/NameServer-POA/
#ORBInitRef.NameService=file://c:/NS_Ref
ORBInitRef.NameService=http://www.x.y.z/~user/NS_Ref
#ORBInitRef.TradingService=http://www.x.y.z/~user/TraderRef

```

The string value for `ORBInitRef.NameService` is a URL for a resource used to set up the JacORB name server. This URL will be used by the ORB to locate the file used to store the name server's object reference (see also chapter 6).

### 3.2.2 Acceptor Exception Event Plugin

This plugin is implemented by `org.jacorb.orb.listener.AcceptorExceptionListener`.

```

package org.jacorb.orb.listener;
public interface AcceptorExceptionListener extends EventListener
    void exceptionCaught(AcceptorExceptionEvent ae);

```

The configuration property is

```
jacorb.acceptor_exception_listener
```

If the server listener thread receives an exception while doing the `ServerSocket.accept()` it will construct a `org.jacorb.orb.listener.AcceptorExceptionEvent` and notify the configured implementation. The Event allows the following to be retrieved:

```

public ORB getORB()
public Throwable getException()

```

The default implementation, `org.jacorb.orb.listener.DefaultAcceptorExceptionListener`, will simply shutdown the ORB on all Errors and for `SSLExceptions` that are thrown before any socket connections have been made. If the developer wishes they may plugin their own for more fine grained control.

In order to detect whether the exception has been thrown on the first attempt or any attempt after that the developer may use the following function within their listener implementation.

```
public void exceptionCaught (AcceptorExceptionEvent ae) {
    ...
    if (((org.jacorb.orb.iiop.IIOPListener.Acceptor)
        ae.getSource()).getAcceptorSocketLoop()) {
        ...
    }
}
```

`getAcceptorSocketLoop` returns false if the event has been thrown on the initial loop, or true on any loop after that.

Note that if the default implementation is used it is possible that due to e.g. an `SSLException` the listener will fail to accept on the server socket after the root POA is resolved which means that the ORB will be shutdown. Therefore future calls on that POA will fail with a 'POA destroyed' message.

### 3.2.3 Codesets

JacORB implements codeset negotiation through `org.jacorb.orb.giop.CodeSet`. Codesets that are currently supported are

- ISO8859\_1
- ISO8859\_15
- UTF8
- UTF16
- UCS2

By default codesets are enabled via the property `jacorb.codeset` but it is possible to disable them. This will give some performance improvements for String marshalling but only for ASCII text.

**Note:** The class `org.jacorb.util.Diagnostic` provides a main method to aid debugging of codeset issues. It will print out the current system encoding values.

### 3.2.4 Compacting Typecodes

Using the property

```
jacorb.compactTypecodes=off
```

causes JacORB to strip off all optional information from Typecode's before marshalling them. This will remove all optional data from the typecode (essentially the equivalent of calling

`get_compact_typecode`). This produces smaller network packages and thereby can give a positive effect on performance.

Disadvantages of this are that the CORBA Notification Service relies on typecodes for complex filter notation and this also may cause interoperability problems with other orbs during typecode comparisons. For instance the comparison of Typecode's that were received across the net with local one's (from a Helper class) using `equal` will fail.

That's because the following holds (see OMG doc):

```
MyTypeHelper.id().equal(MyTypeHelper.id()) => TRUE
MyTypeHelper.id().equal(MyTypeHelper.id()
    .get_compacted_typecode()) => FALSE
```

JacORB will (if compaction is enabled) always invoke `get_compacted_typecode` before marshalling a typecode.

Note: it's not necessary to compare TypeCode's using `equal`. The method `equivalent` does a less strict comparison that omits the optional information.

### 3.2.5 CORBA Object Keys

A JacORB object key consists of `<impl name>/<poa name>/<object oid>`. The lifespan of CORBA objects are defined by the POA policy `LifespanPolicyValue`.

Transient objects are those whose lifespans are bounded by the process in which they were created. Once a transient object has been destroyed any clients still holding references to those objects should receive a `OBJECT_NOT_EXIST`. This applies even if the transient object is recreated as it is a new object reference. To achieve this JacORB replaces the `implname` portion of the key with transient data.

Persistent objects are those that may live beyond the lifetime of the process that created them. The `implname` property should be configured in this case. It should be set to a unique name to form part of the object identity. If it is not set, an exception will be thrown. This property may be configured in the `jacorb.properties` (where an example shows it set to `StandardImplName`) or in the code of the server e.g.

```
/* create and set properties */
java.util.Properties props = new java.util.Properties();
props.setProperty("jacorb.use_imr", "on");
props.setProperty("jacorb.implname", "MyName");

/* init ORB */
orb = org.omg.CORBA.ORB.init(args, props);
```

The `implname` property allows a program to run with a different implementation name so that it will not accept references created by another persistent POA with the same POA name. A common problem

is where the developer has two persistent servers running with the same implname and POA names when one tries to contact the other. Rather than calling server x, server y performs local call. This is because there is no way of distinguishing the two servers; the developer should have used different implnames (e.g. UUIDs).

## Corbaloc with JacORB Implname and CORBA Objects

Normally corbaloc is used to provide a shortcut to refer to CORBA objects. However the stringified key portion corresponds to the octet sequence in the object\_key member of a GIOP Request or LocateRequest header as defined in section 15.4 of CORBA 2.3. Further the key\_string uses the escape conventions described in RFC 2396 to map away from octet values that cannot directly be part of a URL. This means the key string might look like:

```
corbaloc:iiop:10.1.0.4:18000/FooBar/ServiceName/V_3%f1%1c%9b%11%db%b7%e9
    %bdsnQ%ea%85qV_3%f0%1c%9b%11%db%b7%e9%bdsnQ%ea%85TA5%f0%1c%9b%11
    %db%b7%e9%bdsnQ%ea%85
```

With JacORB, for persistent objects, the developer may configure the implname, poa name and object key. This should mean that the corbaloc sequence should be more readable:

```
corbaloc:iiop:10.1.0.4:42811/imr_demo/ImRDemoServerPOA/imr_demo
```

With a transient object the key may look like:

```
corbaloc:iiop:10.1.0.4:42818/2649480905/%00%14%3e45%0d%0b!%10%3e
```

As it is not possible to construct a transient object with a readable key some developers may find it useful to use the objectKeyMap facility within JacORB to refer to their transient objects. Note the objectKey functionality may also be used with persistent objects.

This property provides more readable corbaloc URLs by mapping the actual object key to an arbitrary string. The mapping below would permit clients of a name service to access it using corbaloc::ipaddress:portnum/NameService. The property also accepts the following mappings:

- IOR, resource, jndi, URL (e.g. file, http)

Note that `jacorb.orb.objectKeyMap.name` is configurable both through the `jacorb.properties` file and through the proprietary function

```
ORB::addObjectKey(String name, String)
```

Example usage

```
jacorb.orb.objectKeyMap.NameService=file:///home/rnc/NameSingleton.ior
```

This then allows the corbaloc key portion to simply be 'NameService'.



### 3.2.6 IORMutator

An enhancement has been added to JacORB that allows a developer to alter incoming and outgoing objects at a very low level within the ORB. While the majority of the users would not require this ability, it is useful within scenarios where for instance, a user is running with legacy network elements which have multiple, identical IP addresses. This allows them to mutate the IORs as shown below.

**This is a very powerful ability that must be used with caution. As it operates at the CDRStream level it is easy to break the ORB and cause unpredictable behaviour**

#### Adding a Mutator

The developer should firstly extend the following abstract class.

```
package org.jacorb.orb.IORMutator;
public abstract class IORMutator
    protected org.omg.ETF.Connection connection;

    public abstract IOR mutateIncoming (IOR object);
    public abstract IOR mutateOutgoing (IOR object);
```

The classname should then be specified in the property

```
jacorb.iormutator
```

The IORMutator class also has a `org.omg.ETF.Connection connection` variable. This variable will be updated with the current transport information for the respective streams. Note, altering the information within the transport is undefined. The `mutateIncoming` operation will be called for `CDRInputStream` operations and the `mutateOutgoing` for `CDROutputStream` operations.

### 3.2.7 Listen Endpoints

The command-line option `-ORBListenEndpoints` can be used to instruct a server ORB to listen for requests on network interfaces specified by endpoints. It is implemented specifically for the IIOP protocol (`iiop` and `ssliop`), and it will override the network configuration properties in the property file.

An `-ORBListenEndpoints` endpoint specification has the form:

```
-ORBListenEndpoints endpoint
```

And, the endpoint has the form: An endpoint specification has the form:

```
protocol://V.v@addr1, ..., W.w@addrN
```

where `V.v` and `W.w` are optional protocol versions for each address. An example of an IIOP endpoint is:

```
iiop://hostname:port
```

Sets of endpoints may be specified using multiple `-ORBListenEndpoints` options or by delimiting endpoints with a semi-colon (;). For example,

```
-ORBListenEndpoints iiop://localhost:9999 -ORBListenEndpoints uiop:///tmp/my
```

is equivalent to:

```
-ORBListenEndpoints 'iiop://localhost:9999;uiop:///tmp/mylocalsock'
```

Notice the single quotes (') in the latter option specification. Single quotes are needed to prevent the shell from interpreting text after the semi-colon as another command to run.

If an endpoint is specified having the host omitted as the following:

```
-ORBListenEndpoints iiop://:32000
```

then a wildcard endpoint will be created for the specified protocol where the server ORB will listen for requests on all listenable network interfaces.

If an endpoint is specified having the port number omitted as the following:

```
-ORBListenEndpoints iiop://fujisan:
```

then an endpoint will be created on the host named fujisan having the port chosen automatically.

## IIOP Endpoints

IIOP endpoints have the form:

```
-ORBListenEndpoints iiop://V.v@hostname1:port1,...,W.w@hostname2:port2
```

where "V.v" and "W.w" are the IIOP protocol versions associated with the given address (hostname:port pair). Currently supported versions are 1.0, 1.1, and 1.2. For example,

```
-ORBListenEndpoints iiop://inuyama:12345
```

would instructs the server ORB to listen on the host named inuyama at port 12345.

## SSLIIOP Endpoints

An SSLIIOP endpoint is an extension of the IIOP endpoint. For example,

```
-ORBListenEndpoints iiop://inuyama:12345/ssl_port=44444
```

means that an IIOP endpoint would be opened on port 12345 and an SSLIIOP on port 44444 on the host inuyama. Please note that the protocol label in the above example is iiop and not ssliiop.

### 3.2.8 Loading Classes and Resources

JacORB has two different policies it may use to load classes and resources. By default it will attempt to load using the thread context class loader. To support integration in some deployment scenarios with specialised class loader schemes it is also possible to configure to use `Class.forName` where the class loader is the defining class loader of the current class.

To configure this the following property must be set as a JVM system property

```
jacorb.classloaderpolicy=[tccl|forname]
```

Note that this property MUST be set before any calls to `org.omg.*` or `org.jacorb.*` code. Setting this to 'tccl' will mean JacORB will use the thread context class loader to resolve classes and resources. Setting it to 'forname' means that JacORB will use the defining class loader. Internally JacORB will use this pseudocode:

```
if (useTCCL) {
    return Thread.currentThread().getContextClassLoader().loadClass(name);
} else {
    return Class.forName(name);
}
```

For more information on JacORB class loading see [27](#).

### 3.2.9 Logging

JacORB writes logging information through SLF4J, which is a logging facade that can interface with arbitrary backend logging systems such as Log4J, JCL, or JDK logging. To switch to a different logging system, all that needs to be done is to put a different library on the classpath.

JacORB does not usually attempt to configure the external logging system. That means it is left to you to provide a configuration for it, for example to set the log verbosity or to configure log file names. This is done in a way that is specific to the particular logging system used, e.g. via property files. As an added convenience, there is also a hook in JacORB that allows you to make some settings in the external logging system based on the configuration of JacORB itself, for example to choose log file names based on the implementation name of the server.

The default logging system selected in the JacORB distribution is JDK logging. This is because it is already present in the JDK, and JacORB therefore does not need to ship any other library. A sample configuration for JDK logging is provided, which makes it easy to specify log file names, log rotation parameters, and the like.

#### Logging Conventions

JacORB logs to a hierarchy of loggers with a root logger named `org.jacorb`. All sub-loggers have names that start with this prefix, e.g. `org.jacorb.orb`, `org.jacorb.config`, and so on. Settings

that apply to the root logger usually also apply to all loggers below in the hierarchy (depending on the actual logging system used).

It is possible to split the logging hierarchy based on the implementation name of the ORB instance. Different ORBs will then log to different loggers, which can be configured independently. To do this, set the property `jacorb.log.split_on_implname` to `true`. Then, if the property `jacorb.implname` is set for an ORB instance, the loggers for that ORB all start with the prefix `jacorb.implname.`, rather than just `jacorb.`.

SLF4J defines five different logging levels: error, warn, info, debug, and trace. These levels are mapped to the log levels of the underlying logging system. For JDK logging, the mapping is error → SEVERE, warn → WARNING, info → INFO, debug → FINE, and trace → FINEST. In JacORB's code, the SLF4J log levels are used according to the following conventions:

**error** Events which suggest that there is a bug in JacORB or in user code. This includes, but is not limited to, “fatal errors” which will lead to termination of the program.

**warn** Events that demand attention, but which are handled properly according to the CORBA spec. For example, abnormal termination of a connection, reaching of a resource limit (queue full), and the like.

**info** Starting and stopping of subsystems, establishing and closing of connections, registering objects with a POA.

**debug** Information that might be needed for finding bugs in JacORB or user code. Anything that relates to the normal processing path of individual messages.

**trace** Not used in JacORB (and discouraged by the SLF4J team).

## Configuration of JDK Logging

JDK logging is the default in the JacORB distribution and is automatically configured to log to console at *info* level.

The property `jacorb.log.default.verbosity` specifies the level at which messages are logged. The value is a number from 0 to 4, where 0 means no logging (off), 1 means only *error* messages, 2 means *warn* messages, 3 means *info* messages, and 4 means *debug* messages (higher levels also include lower levels). The default is *info* level.

The property `jacorb.logfile` specifies the name of a file to write the log to. If the `jacorb.logfile` property is not set, output will be sent to the terminal. If the `jacorb.logfile` property is set to an explicit filename then output will be sent to that file. Note that it is NOT recommended that multiple JVM processes send output to the same file as this could lead to file corruption. Alternatively if the `jacorb.logfile` property ends in `$implname` e.g.

```
jacorb.logfile=c:/tmp/$implname
```

and the `jacorb.implname` property has been set, output will be logged to a file with the same name as the `jacorb.implname` property value. See section 3.2.5 for more information

on the `jacorb.implname` property. If `jacorb.logfile.append` is set it will append to the file rather than overwriting it. It is also possible to specify the maximum size of the logfile (through `jacorb.logfile.maxLogSize`) and the number of logfiles to use (through `jacorb.logfile.rotateCount`).

The default formatting of JDK logs is quite verbose, using two lines of output for every log entry. We have provided a `LogFormatter` class that gives a more succinct output. This class is named `org.jacorb.config.JacORBLogFormatter` and is used whenever JacORB configures the logging system itself.

It is possible to modify the output of the Formatter through `jacorb.logfile.showThread` (whether to output thread ID), `jacorb.logfile.showSrcInfo` (whether to display class and method information) and finally `jacorb.logfile.clockFormat`. This last option defaults to `NONE` and may be `NONE`, `TIME` (display time in log messages) or `DATE_TIME` (display date and time in log messages).

For any more sophisticated configuration you need to configure JDK logging directly. To do this prepare a configuration file such as the one found in `JACORB_HOME/etc/logging_properties.template` with your settings. The name of this file needs to be passed to the JVM at startup, for example by providing the following command line option:

```
-Djava.util.logging.config.file=/path/to/config-file
```

## Using another Logging System

The SLF4J facade is implemented in two Java libraries, a generic one and a backend-specific one. The generic library is named `slf4j-api-1.6.4.jar` (or any other version), and the backend-specific library is named `slf4j-jdk14-1.6.4.jar` (for JDK logging), or `slf4j-log4j12-1.6.4.jar` for Log4J, and the like. To switch to a different logging system, the backend-specific library of SLF4J needs to be replaced, and the implementation library for that backend needs to be added as well. So for example, to use Log4J, the following libraries need to be on the classpath: `slf4j-api-1.6.4.jar`, `slf4j-log4j-1.6.4.jar`, and `log4j-1.2.15.jar`. The JacORB distribution only ships with the generic SLF4J library and the JDK adapter library. Other libraries need to be downloaded from the SLF4J site.

When using another logging system besides JDK logging, JacORB does not attempt to configure log verbosity or log file names by itself, as described in the previous section. This means that features such as choosing log file names based on implementation names are not available for other logging systems. You can however configure this explicitly, for example by using the `split-on-implname` feature described above. For more sophisticated needs, it is also possible to provide a `LoggingInitializer` class, which is a hook provided by JacORB to allow configuration of a logging system based on the JacORB configuration. The class needs to extend

the class `org.jacorb.config.LoggingInitializer` and the name of the class needs to be specified in the property `jacorb.log.initializer`.

**Note:** If using Maven as described in 5 then the `slf4j-jdk14` is a default compile *and* runtime dependency. To replace the `slf4j-jdk14` with another implementation in this situation it should be excluded from the `jacorb` dependency e.g.

```
<dependencies>
  <dependency>
    <groupId>org.jacorb</groupId>
    <artifactId>jacorb</artifactId>
    <version>${version.jacorb}</version>
    <exclusions>
      <exclusion>
        <groupId>org.slf4j</groupId>
        <artifactId>slf4j-jdk14</artifactId>
      </exclusion>
    </exclusions>
  </dependency>
</dependencies>
```

## POA Monitor

The `jacorb.poa.monitoring` property determines whether the POA should bring up a monitoring GUI for servers that let you examine the dynamic behavior of your POA, e.g. how long the request queue gets and whether your thread pool is big enough. Also, this tool lets you change the state of a POA, e.g. from *active* to *holding*. Please see chapter 7 on the POA for more details.

## 3.2.10 Network and Sockets

### Threading

It has been found that under some conditions of very heavy thread use, A JacORB client interacting with the Implementation repository can encounter a several Location Forward messages related to the same Delegate. As documented in bug 915, some of these redundant Location Forward messages can cause requests that were already sent to the actual server to be resent. If the request has some side effect, this duplication is a problem. To solve this issue profile discriminated ReplyGroup have been implemented. A reply group is a collection of reply receivers that are associated with a specific profile. A single Delegate may have multiple active reply groups, a Location Forward handled by a reply receiver will only impact the members of its group. This will be seen when a new group is created, which will be the first time a Delegate is used, or in

response to a Location Forward message. Groups are removed from the collection when the last member is removed.

## IP Addresses

On a multihomed machine the IOR will contain only one of the configured IP address (even if `OAIAddr` or `jacorb.ior_proxy_host` is used). In order to add both IP addresses the developer could use an `IORInterceptor` to either:

- add a second `IIOPProfile` with the alternate IP address and implement another `ProfileSelector` to select this alternate address. See Chapter 20.
- add a `TAG_ALTERNATE_IIOP_ADDRESS` component to the existing `IIOPProfile` and set network connection timeouts correctly so client connection attempts to the wrong IP will eventually fail.

## NAT and firewalls

Network Address Translation (NAT) frequently causes a lot of problems if internal CORBA objects need to be accessed from outside the NAT network. Cause of these problems is that object IORs contains host's IP address but internal (inside the NAT) IPs are not accessible from outer network. Simplest solution is using the `jacorb.ior_proxy_host` and DNS names instead of IP addresses. E.g. we have the `192.168.10.*` network managed by NAT. Its gateway has inner IP: `192.168.10.1` and outer IP: `10.30.102.67`. Here are 2 cases:

- Client JacORB application. No additional adjustments need to be done for the client application except firewall (if exists) configuration to allow passing the outgoing connection to the server object(s).
- Server or acting both client and server JacORB application. There is additional adjustments are required.

To make server object behind the NAT accessible from outer network the following configuration steps need to be done:

- Check that DNS name for the host is set. It should be mapped e.g. to the `192.168.10.128` IP inside NAT and to `10.30.102.67` outside the NAT.
- Update the `jacorb.properties` file (host has 'server-host' DNS name for example). Set following properties to:

```
jacorb.ior_proxy_host=server-host
jacorb.dns.enable=on
```

- Choose and define the server object's port (this will allow to easy port mapping by NAT and firewall). This could be done either by `jacorb.properties` file editing. e.g.:

```
OAPort=57998
```

where 57998 is pre-defined port number or by using the `-DOAPort=57998` command line parameter. Note if `OAPort` parameter is defined in `jacorb.properties` it will be used for all server objects that are using the same `jacorb.properties` file. Thus, for many server objects command line parameter is more applicable. Also, remember that ports with numbers below the 1024 are treated as system ports and require root privileges for their creation.

- Setup port forwarding in NAT and firewall according to their configuration guides. Note that port numbers should be the same, e.g. if server uses 15242 port it should have bound to the 15242 gateway port.

If Implementation repository is used the corresponding properties `jacorb.imr.iior_proxy_host` and `jacorb.imr.iior_proxy_port` need to be defined similar to the `jacorb.iior_proxy_host` and `jacorb.iior_proxy_port`.

Also, using the `jacorb.iior_proxy_address` property is more convenient but it should be defined for each server object independently to prevent errors during ports creation.

Parameter `jacorb.dns.force_resolve` allow to controlling host's Fully Qualified Domain Names (FQDN) resolution. If there is necessity to use only "short" DNS names this parameter need to be set to 'off' value. Otherwise the canonical (full) hosts DNS names will be used in IORs by default.

## Ports

JacORB provides a number of socket factories to allow control over the way sockets are created on both the client and the server side.

On the server side JacORB uses `jacorb.net.server_socket_factory` and `jacorb.ssl.server_socket_factory` to control the creation of sockets.

- `org.jacorb.orb.factory.DefaultServerSocketFactory`. Default non-ssl implementation which will pick any available port.
- `org.jacorb.orb.factory.PortRangeServerSocketFactory` which together with the min and max values specifies a port range to use.
- `org.jacorb.security.ssl.sun_jsse.SSLServerSocketFactory` is the default ssl implementation.

Note that it is also possible to override the port selection using `OAPort` or `OASSLPort`.

On the client side JacORB uses `jacorb.net.socket_factory` and `jacorb.ssl.socket_factory` to control the creation of sockets.

- `org.jacorb.orb.factory.DefaultSocketFactory` Default non-ssl implementation which will pick any available port.



- `org.jacorb.orb.factory.FixedAddressSocketFactory` which will pick a fixed port.
- `org.jacorb.orb.factory.PortRangeSocketFactory` which together with the min and max values specifies a port range to use.
- `org.jacorb.security.ssl.sun_jsse.SSLSocketFactory` is the default ssl implementation.

### Custom socket factories

You may plug in custom socket factories that'll be used by JacORB to create sockets and server sockets. Each factory needs to implement a JacORB specific interface. To make your factory available to JacORB you need to set the appropriate configuration property to the classname of your custom factory. See the following sections for the available factories and their details. Please also see the javadoc documentation of the specified interfaces for the contract your custom factories must adhere to. For convenience JacORB also offers some abstract base classes that pre-implement some functionality and that you may choose to subclass.

**Socket Factory** This factory is used by JacORB to create an outgoing non-SSL connection.

Table 3.1: Socket Factory Configuration

property	<code>jacorb.net.socket_factory</code>
implemented interface	<code>org.jacorb.orb.factory.SocketFactory</code>
base class	<code>org.jacorb.orb.factory.AbstractSocketFactory</code>

**Server Socket factory** This factory is used by JacORB to create a server socket for incoming non-SSL connections.

Table 3.2: Server Socket Factory Configuration

property	<code>jacorb.net.server_socket_factory</code>
implemented interface	<code>org.jacorb.orb.factory.ServerSocketFactory</code>
base class	<code>org.jacorb.orb.factory.AbstractSocketFactory</code>

**SSL Socket Factory** This factory is used by JacORB to create an outgoing SSL connection.

Table 3.3: SSL Socket Factory Configuration

property	<code>jacorb.ssl.socket_factory</code>
implemented interface	<code>org.jacorb.orb.factory.SocketFactory</code>

**SSL Server Socket factory** This factory is used by JacORB to create a server socket for incoming SSL connections.

Table 3.4: SSL Server Socket Factory Configuration

property	jacorb.ssl.server_socket_factory
implemented interface	org.jacorb.orb.factory.ServerSocketFactory

### 3.2.11 Network Event Logging

An enhancement has been added to JacORB that allows a developer to monitor TCP and SSL connections. Note that for both of these implementations full information may only be retrieved with a successful connection; e.g. if the connection could not be established there will be no certificates.

#### TCP Monitoring

To monitor TCP connections a developer should implement the following interface

```
package org.jacorb.orb.listener;
public interface TCPConnectionListener extends EventListener
    void connectionOpened(TCPConnectionEvent e);
    void connectionClosed(TCPConnectionEvent e);
```

The classname should then be specified in the property

```
jacorb.net.tcp_listener
```

The standard java event interface is followed; the developer's code will receive the TCPConnectionEvent which allows the following information to be retrieved:

```
public String getLocalIP()
public int getLocalPort()
public String getRemoteIP()
public int getRemotePort()
```

Note that the TCPConnectionEvent extends java.util.EventObject and the EventObject.getSource operation will return the IIOPConnection of the TCP connection.

#### SSL Monitoring

To monitor SSL sessions a developer should implement the following interface

```
package org.jacorb.orb.listener;
public interface SSLSessionListener extends EventListener
    void sessionCreated(SSLSessionEvent e);
    void handshakeException(SSLSessionEvent e);
    void keyException(SSLSessionEvent e);
    void peerUnverifiedException(SSLSessionEvent e);
    void protocolException(SSLSessionEvent e);
    void sslException(SSLSessionEvent e);
```

The classname should then be specified in the property

```
jacorb.security.ssl.ssl_listener
```

The standard java event interface is followed; the developer's code will receive the `SSLSessionEvent` which allows the following information to be retrieved:

```
public String getLocalIP()
public int getLocalPort()
public String getRemoteIP()
public int getRemotePort()
public String getRemoteDN()
public X509Certificate[] getPeerCertificateChain()
```

Note that `getRemoteDN` will simply return a concatenated string of the certificates. For that reason it is deprecated; `getPeerCertificateChain` should be used instead as that allows a developer to extract specific information from the certificate. In order to detect a successful handshake the implementation delegates to the JSSE `javax.net.ssl.HandShakeCompletedListener`. When using JDK1.3 JSSE the JSSE may not throw for instance a `handshakeException` but a `sslException`. Similar to above, `SSLSessionEvent` extends `java.util.EventObject`. The `EventObject.getSource` operation will return the source of the `HandshakeCompletedEvent`.

### 3.2.12 NIO Support

Client side non-blocking I/O support has been added to JacORB. This implementation consists of refactored connector and connection handler that use callbacks to improve asynch performance. The property

```
jacorb.connection.nonblocking=on/off
```

is used to enable this capability. Nonblocking I/O is currently only available for handling client side connections using plain IIOP. Server side support for receiving requests and sending replies is not yet available. Integration of SSL is also not available at this time.

For more details see [19.2](#)

### 3.2.13 Using Object.release

Previously `org.jacorb.orb.Delegate` overrode `java.lang.Object::finalize` in order to call `release` when a client-side stub was garbage collected. In effect it caused the `Delegate` to unregister itself from the underlying `GIOPConnection` and if there were no other `Delegates` using that connection, it was closed and disposed of altogether.

However, as this had performance and scalability issues the `finalize` was removed. This moves the responsibility to the developer whom is now responsible for calling the `CORBA.release` method themselves.

## 3.3 Configuration Properties

A comprehensive listing and description of the properties which are used to configure JacORB are given in the following tables.

### 3.3.1 ORB Configuration

Table 3.5: ORB Configuration

Property	Description	Type	Default
<code>ORBInitRef.&lt;service&gt;</code>	Properties of this form configure initial service objects which can be resolved via the ORB <code>resolve.initial_references</code> . A variety of URL formats are supported.	URL	unset
<code>org.omg.PortableInterceptor.ORBInitializerClass.&lt;name&gt;</code>	A portable interceptor initializer class instantiated at ORB creation.	class	unset
<code>org.omg.PortableInterceptor.ORBInitializerClass.bidir_init</code>	This portable interceptor must be configured to support bi-directional GIOP	class	unset
<code>jacorb.orb.objectKeyMap.&lt;name&gt;</code>	Maps an object key to an arbitrary string thereby enabling better readability for corbaloc URLs.	string	
<code>jacorb.giop_minor_version</code>	The GIOP minor version number to use for newly created IORs	integer	2
<code>jacorb.retries</code>	Number of retries if connection cannot directly be established	integer	5
<code>jacorb.retry_interval</code>	Time in milliseconds to wait between retries	millisec.	500

Table 3.5: ORB Configuration

Property	Description	Type	Default
<code>jacorb.buffermanager.factory</code>	<p>This parameter allow to define buffer manager factory. Here are 3 options already implemented:</p> <ol style="list-style-type: none"> <li>1. <code>org.jacorb.orb.DefaultBufferManagerFactory</code> that will create default buffer manager implementation</li> <li>2. <code>org.jacorb.orb.JDK15BufferManagerFactory</code> that uses JDK 1.5 (or above) buffer manager implementation based on the soft references (<code>java.lang.ref.SoftReference</code>).</li> <li>3. <code>org.jacorb.orb.NonCachingBufferManagerFactory</code> that uses simple buffer manager implementation without any caching.</li> </ol> <p>Also, custom-made buffer manager factories allowed. They must implement the <code>org.jacorb.orb.BufferManagerFactory</code> interface.</p>	class	<code>org.jacorb.orb.DefaultBufferManagerFactory</code>
<code>jacorb.maxManagedBufSize</code>	<p>This is NOT the maximum buffer size that can be used, but just the largest size of buffers that will be kept and managed. The real value of the maximal managed buffer size in bytes is <math>(2^{**}maxManagedBufSize)</math>. You only need to increase this value if you are dealing with LOTS of LARGE data structures. You may decrease it to make the buffer manager release large buffers immediately rather than keeping them for later reuse</p>	integer	22
<code>jacorb.bufferManagerMaxFlush</code>	<p>Whether to use an additional unlimited size buffer cache for <code>CDROutputStreams</code>. If -1 then off, if zero then this is feature is enabled, if greater than zero then it is enabled and flushed every x seconds</p>	integer	0
<code>jacorb.bufferManagerThreshold</code>	<p>Maximum number of buffers of the same size held in pool.</p>	integer	20.

Table 3.5: ORB Configuration

Property	Description	Type	Default
jacorb.buffermanager.expansionpolicy	<p>This parameter allow to define buffer manager expansion policy. Here are 3 options already implemented:</p> <ol style="list-style-type: none"> <li>1. org.jacorb.orb.buffermanager.DefaultExpansionPolicy that will return new buffer's size that bigger or equal to the requested. Sizes calculation are performed by code: <pre>double multiplier = scale - Math.log (requestedSize) / divider; multiplier = (multiplier &lt; 1.0) ? 1.0 : multiplier; newSize = (int) Math.floor ( multiplier * requestedSize );</pre> <p>where scale and divider parameters are configurable (see description below).</p> </li> <li>2. org.jacorb.orb.buffermanager.LinearExpansionPolicy that returns exactly requested size.</li> <li>3. org.jacorb.orb.buffermanager.DoubleExpansionPolicy that returns new size wich equals requested size * 2.</li> </ol> <p>Also, custom-made buffer manager expansion policies are allowed. They must implement the org.jacorb.orb.buffermanager.BufferManagerExpansionPolicy interface. Please note that expansion policy support is implemented in the default buffer manager implementation (org.jacorb.orb.BufferManager). Custom-made buffer manager implementation need to have their own expansion policy support implementation.</p>	class	org.jacorb.orb.buffermanager.DefaultExpansionPolicy
jacorb.buffermanager.defaultexpansionpolicy.scale	Scale parameter for the org.jacorb.orb.buffermanager.DefaultExpansionPolicy buffer sizes calculation (see the formula above).	float	4
jacorb.buffermanager.defaultexpansionpolicy.divider	Divider parameter for the org.jacorb.orb.buffermanager.DefaultExpansionPolicy buffer sizes calculation (see the formula above).	float	6

Table 3.5: ORB Configuration

Property	Description	Type	Default
<code>jacorb.connection.delay_close</code>	Normally, a jacob server will close the TCP/IP connection right after sending a <code>CloseConnection</code> message. However, it may occasionally happen that the client sends a message into the closed connection because it hasn't handled the <code>CloseConnection</code> yet. To avoid this situation, closing of the TCP/IP connection can be delayed (Delay time is controlled by <code>jacorb.connection.timeout_after_closeconnection</code> specified in msec)	boolean	off
<code>jacorb.connection.client.connect_timeout</code>	Initial timeout for establishing a connection.	millisec	90000
<code>jacorb.connection.client.pending_reply_timeout</code>	Wait the specified number of msec for a reply to a request. If exceeded, a <code>org.omg.CORBA.TIMEOUT</code> exception will be thrown. Not set by default	millisec.	0
<code>jacorb.connection.client.idle_timeout</code>	Client-side timeout. This is set to non-zero in order to close the connection after specified number of milliseconds idle time. Only connections that don't have pending messages are closed, unless <code>jacorb.connection.client.timeout_ignores_pending_messages</code> is turned on.	millisec.	unset
<code>jacorb.connection.client.disconnect_after_systemexception</code>	Disconnect client connections after non recoverable system exception. Note that if this is on client-side connections will be completely closed i.e. both ETF and GIOP layers closed rather than just the ETF transport layer (with the expectation that the object will be called again and the GIOP layer reused). This gives better threading performance at the cost of higher GC.	boolean	on
<code>jacorb.connection.client.timeout_ignores_pending_messages</code>	Controls if client-side idle timeouts take care of pending messages or not. If "on", the connection is closed regardless of any pending messages, and all pending messages are cancelled (resulting in a <code>COMM.FAILURE</code> , unless <code>jacorb.connection.client.retry_on_failure</code> is turned on).	boolean	off

Table 3.5: ORB Configuration

Property	Description	Type	Default
<code>jacorb.connection.client.retry_on_failure</code>	Controls if network failures on existing connections should yield a <code>COMM_FAILURE</code> or should trigger a remarshaling of all pending messages. Note that this should only be used with idempotent operations because the client side ORB has no way of knowing the processing state of the lost request on the server.	boolean	
<code>jacorb.connection.server.timeout</code>	Maximum time in milliseconds that a server keeps a connection open if nothing happens	millisec.	unset
<code>jacorb.connection.server.keepalive</code>	Enable <code>SO_KEEPALIVE</code> on server sockets. If the OS keepalive detects a TCP/IP connection to be broken, the effect is the same as if the TCP/IP connection has been closed gracefully.	boolean	false
<code>jacorb.connection.server.reuse\_address</code>	Whether to enable <code>socket.reuseAddress</code> option.	boolean	false
<code>jacorb.connection.client.keepalive</code>	Enable <code>SO_KEEPALIVE</code> on client sockets. If the OS keepalive detects a TCP/IP connection to be broken, the effect is the same as if the TCP/IP connection has been closed gracefully. All pending replies will receive a <code>COMM_FAILURE</code> .	boolean	false
<code>jacorb.connection.max\_server\_connections</code>	This property sets the maximum number of TCP/IP connections that will be listened on by the server-side ORB. Only effective in conjunction with the other connection management properties. Please see <a href="#">19.2</a> .	integer	unlimited
<code>jacorb.connection.wait\_for\_idle\_interval</code>	This property sets the interval to wait until the next try is made to find an idle connection to close. Only effective in conjunction with the other connection management properties. Please see <a href="#">19.2</a> .	millisec	500
<code>jacorb.listener.server\_socket\_timeout</code>	Sets a timeout on the (SSL) server socket. This is a workaround for JDK 1.3 on linux where a thread blocked on <code>accept()</code> isn't notified when closing that socket. Default is 0, i.e. off. See Java bug #4344135. NOTE: This is only useful in conjunction with the SI&C SSL socket factories.	millisec	0
<code>jacorb.connection.selection\_strategy\_class</code>	This property sets the <code>SelectionStrategy</code> . Only effective in conjunction with the other connection management properties. Please see <a href="#">19.2</a> .	class	



Table 3.5: ORB Configuration

Property	Description	Type	Default
<code>jacorb.connection.statistics_provider_class</code>	This property sets the <code>StatisticsProvider</code> . Only effective in conjunction with the other connection management properties. Please see <a href="#">19.2</a> .	class	
<code>jacorb.connection.delay_close</code>	This property controls the behaviour after sending a <code>GIOP CloseConnection</code> message. If set to “on”, the <code>TCP/IP</code> connection won’t be closed directly. Instead, it is waited for the client to do so first. Please see <a href="#">19.2</a> .	boolean	off
<code>jacorb.connection.non_blocking</code>	This property enables use of non-blocking I/O (NIO) on IIOP based transports. Note that this feature is currently only for client-side connections, and only for plain IIOP - not SSL. There is no technical reason for these restrictions, simply lack of current need.	boolean	off.
<code>jacorb.maxConsecutiveTimeouts</code>	Set an upper bound for multiple write attempts triggered by a timeout. This helps mitigate the loss of pending messages due to momentary network saturation, when a close/reopen of a socket would actually cause even more network congestion.	boolean	off.
<code>jacorb.connection.request.write_timeout</code>	Sets the maximum amount of time in milliseconds a client will spend waiting to write a request. Effective when using blocking I/O to ensure a hung peer will not lock up a the client. A request that cannot be sent before the deadline expires is discarded, the connection is closed, and an exception is raised to the client application.	millisec	0
<code>jacorb.connection.reply.write_timeout</code>	Sets the maximum amount of time in milliseconds a server will spend waiting to write a reply. Effective when using blocking I/O to ensure a hung peer will not lock up a the server. A reply that cannot be sent before the deadline expires is discarded and the connection is closed.	millisec	0

Table 3.5: ORB Configuration

Property	Description	Type	Default
<code>jacorb.listener.server_socket_timeout</code>	Sets a timeout on the (SSL) server socket. This is a workaround for JDK 1.3 on linux where a thread blocked on <code>accept()</code> isn't notified when closing that socket. Default is 0, i.e. off. See Java bug #4344135. NOTE: This is only useful in conjunction with the SI&C SSL socket factories.	millisec	0
<code>jacorb.transport.factories</code>	This property controls which transport plug-ins are available to the ORB. The value is a list of classes that implement the <code>ETF_Factories</code> interface.	comma-separated list of classes	
<code>jacorb.transport.server.listeners</code>	Controls which transports should be offered by JacORB on the server side. The value is a list of numeric profile tags for each transport that should be available on the server side.	comma-separated list of integers	
<code>jacorb.transport.client.selector</code>	Name of a class that selects the transport profile to use for communication on the client side. The value is the fully qualified name of a class that implements <code>org.jacorb.orb.ProfileSelector</code> .	class	
<code>jacorb.reference_caching</code>	Whether or not JacORB caches objects references	boolean	unset
<code>jacorb.hashtable_class</code>	The following property specifies the class which is used for reference caching. <code>WeakHashtable</code> uses <code>WeakReferences</code> , so entries get garbage collected if only the <code>Hashtable</code> has a reference to them. This is useful if you have many references to short-living non-persistent CORBA objects. It is only available for java 1.2 and above. On the other hand the standard <code>Hashtable</code> keeps the references until they are explicitly deleted by calling <code>_release()</code> . This is useful for persistent and long-living CORBA objects	class	<code>Hashtable</code>
<code>jacorb.use_bom</code>	Use GIOP 1.2 byte order markers, since CORBA 2.4-5	boolean	off
<code>jacorb.giop.add_1_0_profiles</code>	Add additional IIOP 1.0 profiles even if using IIOP 1.2	boolean	off
<code>jacorb.dns.enable</code>	Use DNS names in IORs, rather than numeric IP addresses	boolean	off
<code>jacorb.dns.eager_resolve</code>	resolve DNS names in IORs eagerly	boolean	on

Table 3.5: ORB Configuration

Property	Description	Type	Default
<code>jacorb.dns.force_lookup</code>	Forces FQDN host name reverse lookup. Turn off if "short" host name need to be used in IORs	boolean	on
<code>jacorb.compactTypecodes</code>	Whether to send compact typecodes. Options are off or on (full compaction of all optional parameters). See <a href="#">3.2.4</a>	boolean	off
<code>jacorb.cacheTypecodes</code>	Whether to cache read typecodes	boolean	off
<code>jacorb.cachePoaNames</code>	Whether to cache poa names as an optimisation to save reparsing portions of the object key	boolean	off
<code>jacorb.orb_initializer.fail_on_error</code>	Control, if failing ORBInitializers should make the complete <code>ORB.init()</code> fail.	boolean	off
<code>jacorb.acceptor_exception_listener_class</code>	A class implementing interface <code>org.jacorb.orb.listener.AcceptorExceptionListener</code> . The implementation will be notified of any exception caught by the thread doing the <code>ServerSocket.accept()</code> and has the chance of taking appropriate action, e.g. shutting down the ORB. The default implementation will shutdown the ORB on all <code>Errors</code> and <code>SSLEExceptions</code> .	String (class name)	<code>org.jacorb.orb.listener.DefaultAcceptorExceptionListener</code>
<code>jacorb.interop.indirection_encoding_disable</code>	Turn off indirection encoding for repeated typecodes. This fixes interoperability with certain broken ORB's eg. Orbix 2000	boolean	off
<code>jacorb.interop.comet</code>	Enable additional buffer length checking and adjustment for interoperability with Comet CORBA/COM bridge which can incorrectly encode buffer lengths	boolean	off
<code>jacorb.interop.lax_boolean_encoding</code>	Treat any non zero CDR encoded boolean value as true (strictly should be 1 not non zero). This is useful for ORBs such as VisiBroker and ORBacus	boolean	off
<code>jacorb.interop.null_string_encoding</code>	Allow reading and writing of null strings. This can be useful for ORBs such as VisiBroker.	boolean	off
<code>jacorb.net.tcp_listener</code>	Defines a listener for TCP connection events. See <a href="#">3.2.11</a> .	string	disabled
<code>jacorb.enhanced_thread_name</code>	Temporarily adds connection endpoints and time (in milliseconds) that the thread started to the Thread name. To be used to correlate running threads with entries in debug logs.	string	off
<code>jacorb.disableClientOrbPolicies</code>	Disable client side ORB policies for speed.	boolean	off

Table 3.5: ORB Configuration

Property	Description	Type	Default
<code>jacorb.ipv6.hide_zoneid</code>	By default JacORB will remove the ZoneID so IORs will work off-host.	boolean	on
<code>jacorb.avoidIsARemoteCall</code>	Always attempt to search for local repository ID information to avoid the cost of a remote call. In most scenarios this is quicker than the remote call. With some complicated hierarchies it may be quicker to turn this off.	boolean	on
<code>jacorb.locate_on_bind</code>	Query server for object location using a GIOP locate request before first call.	boolean	off
<code>jacorb.native_char_codeset</code>	Overrides the detection from the local environment for the codeset used to transmit characters. Note that this property is only effective once per JVM.	string	off
<code>jacorb.native_wchar_codeset</code>	Overrides the detection from the local environment for the codeset used to transmit wide characters. Note that this property is only effective once per JVM.	string	off
<code>jacorb.codeset</code>	Enabling this will do codeset translation on marshalling and add the TAG.CODE.SETS tagged component. Disabling it will force JacORB to ignore all codeset component info profiles and to disable translation on marshalling. See <a href="#">3.2.3</a>	boolean	on

### 3.3.2 Network Configuration

Table 3.6: Network Configuration

Property	Description	Type	Default
----------	-------------	------	---------

Table 3.6: Network Configuration

Property	Description	Type	Default
<code>jacorb.iior_proxy_address</code>	Used to supply an alternative endpoint in locally created object references. This is intended for servers that export IORs for access from outside a firewall. The general form of the value is <code>&lt;protocol&gt;://&lt;address&gt;</code> . The protocol name in the value must match the protocol(s) used by the server. For example: <code>iiop://myhost:1234</code> . The given address is inserted into every IOR that the local ORB produces, without any check whether the address is valid, except that the protocol must be supported by the ORB, and the address must be parsable for that protocol. This property supercedes <code>jacorb.iior_proxy_host</code> and <code>jacorb.iior_proxy_port</code> .	string	unset
<code>jacorb.iior_proxy_host</code>	The properties <code>jacorb.iior_proxy_host</code> and <code>jacorb.iior_proxy_port</code> have been superceded by <code>jacorb.iior_proxy_address</code> (see above), which is a protocol-independent way of specifying endpoint addresses. The host/port properties are still recognized, but if <code>jacorb.iior_proxy_address</code> is specified, it overrides these properties. Note that the value that ends up in the IOR also is affected by the setting of the property <code>jacorb.dns.enable</code> .	node	unset
<code>jacorb.iior_proxy_port</code>	See <code>jacorb.iior_proxy_host</code> and <code>jacorb.iior_proxy_address</code> above	port	unset
<code>OAAAddress</code>	Used to supply an explicit listener protocol and address for servers. The general form of the value is <code>&lt;protocol&gt;://&lt;address&gt;</code> . The protocol name must match the protocol(s) used by the server. For example: <code>iiop://myhost:1234</code> . This property supercedes <code>OAIAddr</code> and <code>OAPort</code> .	string	unset

Table 3.6: Network Configuration

Property	Description	Type	Default
OAIAddr	<p>The Object Adapter Internet Address: IP address on multi-homed host (this gets encoded in object references).</p> <ul style="list-style-type: none"> <li>Addresses like 127.0.0.X will only be accessible from the same machine!</li> <li>If OAIAddr is not set on a multi-homed host it is operating system/JVM dependant which IP address is selected.</li> <li>If the developer is trying to use callbacks (<i>not bidirectional GIOP</i>) on a multihomed host the client will also require OAIAddr set as it is acting as a server.</li> </ul>	node	unset
OAPort	See OAIAddr above (ignored if OAddress is set)	port	unset
jacorb.net.socket_factory	Sets or defines the socket factory. See section 3.2.10 for details.	class	
jacorb.net.server_socket_factory	Sets or defines the server socket factory. See section 3.2.10 for details.	class	
jacorb.net.socket_factory.port.min	Sets the minimum port number that can be used for an additional supported socket factory. This property is used in conjunction with the <code>jacorb.net.socket_factory.port.max</code> property. These properties enable the factory to traverse firewalls through a fixed port range	integer	unset (disabled)
jacorb.net.socket_factory.port.max	Sets the maximum port number that can be used for the additional supported socket factory. Refer to <code>jacorb.net.socket_factory.port.min</code> above	integer	disabled

### 3.3.3 Logging Configuration

Table 3.7: Logging Configuration

Property	Description	Type	Default
jacorb.orb.print_version	If enabled, the ORB's version number is printed whenever the ORB is initialized.	boolean	off
jacorb.log.default.verbosity	Log levels: 0 = off, 1 = error, 2 = warning, 3 = info, 4 = debug	integer	info

Table 3.7: Logging Configuration

Property	Description	Type	Default
jacorb.logfile	Output destination for diagnostic log file. If not set, diagnostics are sent to standard error.	filename	unset
jacorb.logfile.append	Whether to append to existing log file or overwrite (if file logging)	boolean	off
jacorb.logfile.maxLog Size	Maximum size of logfile. Zero implies no limit.	int	0
jacorb.logfile.rotate Count	Number of logfiles to use.	int	1
jacorb.logfile.showThread	Display thread ID in log messages.	boolean	off
jacorb.logfile.showSrcInfo	Display class and method information in log messages.	boolean	off
jacorb.logfile.clock Format	Display clock information in log messages. May be NONE, TIME or DATE.TIME.	string	NONE
jacorb.log.initializer	Name of a class to initialize logging after the configuration has been read	class	JdkLoggingInitializer
jacorb.debug.dump_outgoing_messages	Hex dump outgoing messages	boolean	off
jacorb.debug.dump_incoming_messages	Hex dump incoming messages	boolean	off

### 3.3.4 POA Configuration

Table 3.8: POA Configuration

Property	Description	Type
jacorb.poa.monitoring	Displays a GUI monitoring tool for servers. Default is off.	boolean
jacorb.poa.thread_pool_max	Maximum thread pool configuration for request processing	integer
jacorb.poa.thread_pool_min	Minimum thread pool configuration for request processing	integer
jacorb.poa.thread_pool_shared	If set use shared thread pool between all POAs. Only with ORB_CTRL_MODEL. Default is off.	boolean
jacorb.poa.threadtimeout	Specifies whether to timeout waiting to acquire a Request-Processor if the thread pool is empty. Defaults to 0 (wait for infinity)	integer

Table 3.8: POA Configuration

Property	Description	Type
<code>jacorb.poa.thread_priority</code>	If set, request processing threads in the POA will run at this priority. If not set or invalid, <code>MAX_PRIORITY</code> will be used. Not set by default.	integer
<code>jacorb.poa.queue_wait</code>	Specifies whether the POA should block when the request queue is full (On), or throw <code>TRANSIENT</code> exceptions (Off). Default is Off.	boolean
<code>jacorb.poa.queue_max</code>	The maximum length of the request queue. If this length has been reached, and further requests arrive, <code>jacorb.poa.queue_wait</code> specifies what to do. Default is 100.	integer
<code>jacorb.poa.queue_listeners</code>	Names of the classes that implement the <code>RequestQueueListener</code> .	string
<code>jacorb.poa.queue_min</code>	If <code>jacorb.poa.queue_wait</code> is On, and the request queue gets full, then the POA blocks until the queue contains no more than <code>queue_min</code> requests. Default is 10.	integer
<code>jacorb.poa.check_reply_end_time</code>	Set this to on for server-side checking of expired <code>ReplyEndTimePolicy</code> . This also applies to <code>RelativeRoundtripTimeoutPolicy</code> . When this is on, the clocks of the server and client machine need to be synchronized. Default is off.	boolean
<code>jacorb.poa.useServantClassLoader</code>	Run servant code in the thread context class loader of the servant class rather than the current class loader (which is defined by the value of <code>jacorb.classloaderpolicy</code> which may use either thread context or <code>forName</code> ). Default is off.	boolean

### 3.3.5 Implementation Repository Configuration

Table 3.9: Implementation Repository Configuration

Property	Description	Type
<code>jacorb.use_imr</code>	Switch on to contact the Implementation Repository (IR) on every server start-up. Default is off. This property must be turned off when the <code>jacorb.use_tao_imr</code> is turned on. If both properties are turned on, an exception will be thrown.	boolean
<code>jacorb.use_tao_imr</code>	Switch on to contact the TAO Implementation Repository (TAO ImR) on every server start-up. Default is off. This property must be turned off when the <code>jacorb.use_imr</code> is turned on. If both properties are turned on, an exception will be thrown.	boolean



Table 3.9: Implementation Repository Configuration

Property	Description	Type
<code>jacorb.use_imr_endpoint</code>	Switch off to prevent writing the IMR address into server IORs. This property is ignored if <code>jacorb.use_imr = off</code> . Default is off.	boolean
<code>jacorb.imr.allow_auto_register</code>	If set to on servers that don't already have an entry on their first call to the IR, will get automatically registered. Otherwise, an <code>UnknownServer</code> exception is thrown. Default is off.	boolean
<code>jacorb.imr.check_object_liveness</code>	If set on the IR will try to ping every object reference that it is going to return. If the reference is not alive, then <code>TRANSPARENT</code> is thrown. Default is off.	boolean
<code>ORBInitRef.ImplementationRepository</code>	The initial reference for the IR.	URL
<code>jacorb.imr.table_file</code>	File in which the IR stores data.	file
<code>jacorb.imr.backup_file</code>	Backup data file for the IR.	file
<code>jacorb.imr.ior_file</code>	File to which the IR writes its IOR. This is usually referred to by the initial reference for the IR (configured above).	file
<code>jacorb.imr.timeout</code>	Time in milliseconds that the implementation will wait for a started server to register. After this timeout is exceeded the IR assumes the server has failed to start. Default is 12000 (2 minutes).	millisec.
<code>jacorb.imr.no_of_poas</code>	Initial number of POAs that can be registered with the IR. This is an optimization used to size internal data structures. This value can be exceeded. Default is 100.	integer
<code>jacorb.imr.no_of_servers</code>	Initial number of servers that can be registered with the IR. This is an optimization used to size internal data structures. This value can be exceeded. Default is 5.	integer
<code>jacorb.imr.port_number</code>	Starts the IMR on a fixed port (equivalent to the <code>-p</code> option).	integer
<code>jacorb.imr.connection_timeout</code>	Time in milliseconds that the IR waits until a connection from an application client is terminated. Default is 2000.	millisec.
<code>jacorb.implname</code>	The implementation name for persistent servers. See <a href="#">3.2.5</a> .	name
<code>jacorb.java_exec</code>	Command used by the IR to start servers.	command

### 3.3.6 Security Configuration

Table 3.10: Security Configuration

Property	Description	Type
<code>jacorb.security.support_ssl</code>	Whether SSL security is supported. Default is off.	boolean

Table 3.10: Security Configuration

Property	Description	Type
OASSSLPort	The port number used by SSL, will be dynamically assigned by default.	port
org.omg.PortableInterceptor.ORBInitializerClass.ForwardInit	Portable interceptor required to support SSL. This interceptor must be set if programs need access to certificates using the CORBA Security API, SSL works also without this interceptor. Not set by default and may be set to org.jacorb.security.ssl.sun_jsse.SecurityServiceInitializer.	class
jacorb.ssl.socket_factory	The qualified classname of the SSL socket factory class. See section 3.2.10 for details.	class
jacorb.ssl.server_socket_factory	The qualified classname of the SSL server socket factory class. See section 3.2.10 for details.	class
jacorb.security.ssl.client.supported_options	SSL client supported options - IIOP/SSL parameters (numbers are hex values, without the leading 0x): <ol style="list-style-type: none"> <li>1. NoProtection = 1</li> <li>2. EstablishTrustInClient = 40</li> <li>3. EstablishTrustInTarget = 20</li> <li>4. Mutual authentication = 60</li> </ol> Default is 0. Please see the programming guide for more explanation.	integer
jacorb.security.ssl.client.required_options	SSL client required options (See IIOP/SSL parameters above). Default is 0.	integer
jacorb.security.ssl.server.supported_options	SSL server supported options (See IIOP/SSL parameters above). Default is 0.	integer
jacorb.security.ssl.server.required_options	SSL server required options (See IIOP/SSL parameters above). Default is 0.	integer
jacorb.security.ssl.corbaloc_ssliop.supported_options	Used in conjunction with jacob.security.ssl.corbaloc_ssliop.required_options. If these properties are set, then two values will be placed in the IOR, "corbaloc:ssliop" and "ssliop". If not set, only EstablishTrustInTarget is used for both supported and required options.	integer
jacorb.security.ssl.corbaloc_ssliop.required_options	Default is 0.	integer

Table 3.10: Security Configuration

Property	Description	Type
<code>jacorb.security.keystore</code>	The name and location of the keystore. This may be absolute or relative to the home directory. NOTE (for Sun JSSE users): The <code>javax.net.ssl.trustStore [Password]</code> properties doesn't seem to take effect, so you may want to add trusted certificates to normal keystores. In this case, please set the property <code>jacorb.security.jsse.trustees_from_ks</code> to on, so trusted certificates are taken from the keystore instead of a dedicated truststore.	file
<code>jacorb.security.keystore_password</code>	The keystore password.	string
<code>jacorb.security.keystore_type</code>	The SSL keystore type. Defaults to JKS.	string
<code>jacorb.security.jsse.server.key_manager_algorithm</code>	The algorithm used to initialise the SSL socket factories. Defaults to SunX509. Change to IbmX509 for IBM JDKs.	string
<code>jacorb.security.jsse.server.trust_manager_algorithm</code>	The algorithm used to initialise the SSL socket factories. Defaults to SunX509. Change to IbmX509 for IBM JDKs.	string
<code>jacorb.security.jsse.client.key_manager_algorithm</code>	The algorithm used to initialise the SSL socket factories. Defaults to SunX509. Change to IbmX509 for IBM JDKs.	string
<code>jacorb.security.jsse.client.trust_manager_algorithm</code>	The algorithm used to initialise the SSL socket factories. Defaults to SunX509. Change to IbmX509 for IBM JDKs.	string
<code>jacorb.security.jsse.client.trust_manager</code>	A user defined <code>javax.net.ssl.TrustManager</code> implementation class name. Will be used to initialise the <code>SSLContext</code> . See JSSE docs for <code>javax.net.ssl.SSLContext#init()</code> . Must be capable of instantiation via a no arg constructor.	string
<code>jacorb.security.jsse.server.trust_manager</code>	A user defined <code>javax.net.ssl.TrustManager</code> implementation class name. Will be used to initialise the <code>SSLContext</code> . See JSSE docs for <code>javax.net.ssl.SSLContext#init()</code> . Must be capable of instantiation via a no arg constructor.	string
<code>jacorb.security.jsse.trustees_from_ks</code>	Sun JSSE specific settings: Use the keystore to take trusted certificates from. Default is off.	boolean
<code>jacorb.security.ssl.server.cipher_suites</code>	A comma-separated list of cipher suite names which must NOT contain whitespaces. See the JSSE documents on how to obtain the correct cipher suite strings.	string
<code>jacorb.security.ssl.client.cipher_suites</code>	See <code>jacorb.security.ssl.server.cipher_suites</code> above.	string

Table 3.10: Security Configuration

Property	Description	Type
<code>jacorb.security.ssl.client.protocols</code>	Sun JSSE specific settings: Comma separated list of names of protocols to be set. See the JSSE documentation for <code>javax.net.ssl.SSLSocket#setEnabledProtocols()</code> .	string
<code>jacorb.security.ssl.server.protocols</code>	Sun JSSE specific settings: Comma separated list of names of protocols to be set. See the JSSE documentation for <code>javax.net.ssl.SSLSocket#setEnabledProtocols()</code> .	string
<code>jacorb.security.random.classPlugin</code>	Classname for secure random plugin. See <a href="#">13.3</a>	string
<code>jacorb.security.ssl.ssl_listener</code>	Defines a listener for SSL connection events. See <a href="#">3.2.11</a> .	string
<code>jacorb.security.ssl.always_open_unsecured_endpoint</code>	Default is FALSE. The secure interoperability spec states that targets that require SSL shall not open (or publicise in their IORs) an unsecured listen port. Some ORBs (we're looking at you, MICO) apparently don't like this. Setting this switch to TRUE will override the correct behaviour for interoperability. Attempts to access the unsecured port should be met with a NO_PERMISSION exception.	boolean

Table 3.11: Security Attribute Service (SAS) Configuration

Property	Description	Type
<code>jacorb.security.sas.contextClass</code>	Defines the specific SAS context generator/validator. Currently supported contexts include: <ol style="list-style-type: none"> <li>1. NullContext - Sends a NULL SAS Context</li> <li>2. GssUpContext - Uses GSSUP security</li> <li>3. KerberosContext - uses Kerberos security</li> </ol> At least one context must be selected for SAS support	string
<code>rg.omg.PortableInterceptor.ORBInitializerClass.SAS</code>	This initializer installs the SAS interceptors.	string
<code>rg.omg.PortableInterceptor.ORBInitializerClass.GSSUPProvider</code>	This option is used for GSSUP security and sets up the GSS Provider.	string
<code>jacorb.security.sas.stateful</code>	Whether to support stateful contexts. Default true.	boolean
<code>jacorb.security.sas.tss.requires_sas</code>	Whether SSL connection is required. Default false.	boolean

### 3.3.7 Name Service Configuration

Table 3.12: Name service Configuration

<b>Property</b>	<b>Description</b>	<b>Type</b>
jacorb.naming.log.verbosity	The log level for the name service. Defaults to jacobd.log.default.verbosity	0-4
jacorb.naming.purge	Whether non-active references are purged from name service when list operation is invoked. Default is off	boolean
jacorb.naming.noping	Whether resolve should return references without trying to ping them to see if they're still alive first. Default is ping (off)	boolean
jacorb.naming.ior_filename	The file where the name server drops its IOR (default unset)	string
jacorb.naming.print_ior	Whether to print the IOR to console (Default off)	boolean
jacorb.naming.db_dir	Where to store the naming data files. (Default current directory)	string



## 4 Getting Started

Before we explain an example in detail, we look at the general process of developing CORBA applications with JacORB. We'll follow this roadmap when working through the example. The example can be found in `demo/grid` which also contains a build file so that the development steps do not have to be carried out manually every time. Still, you should know what is going on.

As this document gives only a short introduction to JacORB programming and does not cover all the details of CORBA IDL, we recommend that you also look at the other examples in the `demo/` directory. These are organized so as to show how the different aspects of CORBA IDL can be used with JacORB.

### 4.1 JacORB development: an overview

The steps we will generally have to take are:

1. write an IDL specification.
2. compile this specification with the IDL compiler to generate Java classes (Java interfaces, helper and holder classes, as well as stubs and skeletons).
3. write an implementation for the Java interface generated in step 2
4. write a “Main” class that instantiates the server implementation and registers it with the ORB
5. write a client class that retrieves a reference to the server object and makes remote invocations, i.e. CORBA calls.

### 4.2 IDL specifications

Our example uses a simple server the definition of which should be clear if you know IDL. Its interface is given in `server.idl`. All the source code for this example can be found in `jacorb-3.6/demo/grid`.

```
// server.idl
// IDL definition of a 2-D grid:
```

```
module demo
{
  module grid
  {
    interface MyServer
    {
      typedef fixed <5,2> fixedT;

      readonly attribute short height; // height of the grid
      readonly attribute short width; // width of the grid

      // set the element [n,m] of the grid, to value:
      void set(in short n, in short m, in fixedT value);

      // return element [n,m] of the grid:
      fixedT get(in short n, in short m);

      exception MyException
      {
        string why;
      };

      short opWithException() raises( MyException );
    };
  };
};
```

## 4.3 Generating Java classes

Feeding this file into the IDL compiler

```
$ idl -d ./generated server.idl
```

produces a number of Java classes that represent the IDL definitions. This is done according to a set of rules known as the IDL-to-Java language mapping as standardized by the OMG. If you are interested in the details of the language mapping, i.e. which IDL language construct is mapped to which Java language construct, please consult the specifications available from <http://www.omg.org>. The language mapping used by the JacORB IDL compiler is the one defined in CORBA 2.3 and is explained in detail in [?]. For practical usage, please consult the examples in the demo directory.

The most important Java classes generated by the IDL compiler are the interfaces `MyServer` and `MyServerOperations`, and the stub and skeleton files `_MyServerStub`, `MyServerPOA` and `MyServerPOATie`. We will use these classes in the client and server as



well as in the implementation of the grid's functionality and explain each in turn.

Note that the IDL compiler will produce a directory structure for the generated code that corresponds to the module structure in the IDL file, so it would have produced a subdirectory `demo/grid` in the current directory had we not directed it to put this directory structure to `./generated` by using the compiler's `-d` switch. Where to put the source files for generated classes is a matter of taste. Some people prefer to have everything in one place (as using the `-d` option in this way achieves), others like to have one subdirectory for the generated source code and another for the output of the Java compiler, i.e. for the `.class` files.

## 4.4 Implementing the interface

Let's try to actually provide an implementation of the functionality promised by the interface. The class which implements that interface is called `gridImpl`. Apart from providing a Java implementation for the operations listed in the IDL interface, it has to inherit from a generated class that both defines the Java type that represents the IDL type `MyServer` and contains the code needed to receive remote invocations and return results to remote callers. This class is `MyServerPOA`.

You might have noticed that this approach is impractical in situations where your implementation class needs to inherit from other classes. As Java only has single inheritance for implementations, you would have to use an alternative approach — the “tie”-approach — here. The tie approach will be explained later.

Here is the Java code for the grid implementation. It uses the Java library class `java.math.BigDecimal` for values of the IDL fixed-point type `fixedT`:

```
package demo.grid;

/**
 * A very simple implementation of a 2-D grid
 */

import demo.grid.MyServerPackage.MyException;

public class gridImpl
    extends MyServerPOA
{
    protected short height = 31;
    protected short width = 14;
    protected java.math.BigDecimal[][] mygrid;

    public gridImpl()
    {
```

```
mygrid = new java.math.BigDecimal[height][width];
for( short h = 0; h < height; h++ )
{
    for( short w = 0; w < width; w++ )
    {
        mygrid[h][w] = new java.math.BigDecimal("0.21");
    }
}

public java.math.BigDecimal get(short n, short m)
{
    if( ( n <= height ) && ( m <= width ) )
        return mygrid[n][m];
    else
        return new java.math.BigDecimal("0.01");
}

public short height()
{
    return height;
}

public void set(short n, short m, java.math.BigDecimal value)
{
    if( ( n <= height ) && ( m <= width ) )
        mygrid[n][m] = value;
}

public short width()
{
    return width;
}

public short opWithException()
    throws demo.grid.MyServerPackage.MyException
{
    throw new demo.grid.MyServerPackage.MyException("This is only a test exc
}
}
```

### 4.4.1 The Tie Approach

If your implementation class cannot inherit from the generated servant class `MyServerPOA` because, e.g., you need to inherit from another base class, you can use the tie approach. Put simply, it replaces inheritance by delegation. Instead of inheriting from the generated base class, your implementation needs to implement the generated operations interface `MyServerOperations`:

```
package demo.grid;

import demo.grid.MyServerPackage.MyException;

public class gridOperationsImpl
    implements MyServerOperations
{
    ...
}
```

Your server is then written as follows:

```
package demo.grid;

import java.io.*;
import org.omg.CosNaming.*;

public class TieServer
{
    public static void main( String[] args ) throws Exception
    {
        org.omg.CORBA.ORB orb = org.omg.CORBA.ORB.init(args, null);
        org.omg.PortableServer.POA poa =
            org.omg.PortableServer.POAHelper.narrow(orb.resolve_initial_referenc

        org.omg.CORBA.Object o =
            poa.servant_to_reference( new MyServerPOATie(new GridOperationsImpl(

        poa.the_POAManager().activate();

        PrintWriter ps = new PrintWriter(new FileOutputStream(new File( args[0]
        ps.println( orb.object_to_string( o ) );
        ps.close();

        if (args.length == 2)
        {
            File killFile = new File(args[1]);
            while(!killFile.exists())
```

```
        {
            Thread.sleep(1000);
        }
        orb.shutdown(true);
    }
    else
    {
        orb.run();
    }
}
}
```

## 4.5 Writing the Server

To actually instantiate a `gridImpl` object which can be accessed remotely as a CORBA object of type `MyServer`, you have to instantiate it in a main method of some other class and register it with a component of the CORBA architecture known as the *Object Adapter*. Here is the class `Server` which does all that is necessary to activate a CORBA object of type `MyServer` from a Java `gridImpl` object:

```
package demo.grid;

import java.io.*;
import org.omg.CosNaming.*;

public class Server
{
    public static void main( String[] args ) throws Exception
    {
        org.omg.CORBA.ORB orb = org.omg.CORBA.ORB.init(args, null);
        org.omg.PortableServer.POA poa =
            org.omg.PortableServer.POAHelper.narrow(orb.resolve_initial_referenc

        poa.the_POAManager().activate();

        org.omg.CORBA.Object o =
            poa.servant_to_reference( new GridImpl() );

        PrintWriter ps = new PrintWriter(new FileOutputStream(new File( args[0]
        ps.println( orb.object_to_string( o ) );
        ps.close();

        if (args.length == 2)
        {
            File killFile = new File(args[1]);
```

```
        while(!killFile.exists())
        {
            Thread.sleep(1000);
        }
        orb.shutdown(true);
    }
    else
    {
        orb.run();
    }
}
}
```

After initializing the ORB we need to obtain a reference to the object adapter — the POA — by asking the ORB for it. The ORB knows about a few initial references that can be retrieved using simple names like “RootPOA”. The returned object is an untyped reference of type `CORBA.Object` and thus needs to be narrowed to the correct type using a static method `narrow()` in the helper class for the type in question. We now have to activate the POA because any POA is created in “holding” state in which it does not process incoming requests. After calling `activate()` on the POA’s `POAManager` object, the POA is in an active state and can now be asked to create a CORBA object reference from a Java object also known as a `Servant`.

In order to make the newly created CORBA object accessible, we have to make its object reference available. There are a variety of ways of doing this. One option, as demonstrated above is to write the IOR reference to a file and distribute that. Another is to use a publicly accessible directory service, the naming server. A reference to the naming service is obtained by calling `orb.resolve_initial_references("NameService")` on the ORB and narrowing the reference using the `narrow()` method found in class `org.omg.CosNaming.NamingContextExtHelper`. Having done this, you should call the `bind()` operation on the name server. The name for the object which has to be supplied as an argument to `bind()` is not simply a string. Rather, you need to provide a sequence of `CosNaming.NameComponents` that represent the name. The Extended Name Server interface that provides a more convenient conversion operation from strings to `Names`.

## 4.6 Writing a client

Finally, let’s have a look at the client class which invokes the server operations:

```
package demo.grid;

import org.omg.CosNaming.*;

public class Client
{
```

```
public static void main(String args[]) throws Exception
{
    MyServer grid;

    org.omg.CORBA.ORB orb = org.omg.CORBA.ORB.init(args, null);

    BufferedReader reader = new BufferedReader(new FileReader(args[0]));

    grid = MyServerHelper.narrow(orb.string_to_object(reader.readLine()));

    short x = grid.height();
    System.out.println("Height = " + x);

    short y = grid.width();
    System.out.println("Width = " + y);

    x -= 1;
    y -= 1;

    System.out.println("Old value at (" + x + ", " + y + "): " +
        grid.get(x,y));

    System.out.println("Setting (" + x + ", " + y + ") to 470.11");

    grid.set(x, y, new java.math.BigDecimal("470.11"));

    System.out.println("New value at (" + x + ", " + y + "): " +
        grid.get(x,y));

    try
    {
        grid.opWithException();
    }
    catch (demo.grid.MyServerPackage.MyException ex)
    {
        System.out.println("MyException, reason: " + ex.why);
    }

    orb.shutdown(true);
    System.out.println("done. ");
}
}
```

After initializing the ORB, the client needs to obtain a reference to the “grid” service. In the example above it reads the IOR argument passed to the Client. Another method would be to locate the reference

using the name service. Again, resolving the name is done by getting a reference to the naming service by calling `orb.resolve_initial_references("NameService")` and querying the name server for the "grid" object by calling `resolve()`. The argument to the resolve operation is, again, a string that is converted to a `Name`. The result is an object reference of type `org.omg.CORBA.Object` which has to be narrowed to the type we are expecting, i.e. `MyServer`.

## 4.7 Running the Example Application

After compiling everything we're now ready to actually run the server and the client on different (virtual) machines. You can now launch the server:

```
$ jaco demo.grid.Server
```

The client can be invoked by typing:

```
$ jaco demo.grid.Client
```

Running the client after starting the server produces the following output on your terminal:

```
Height = 31
Width = 14
Old value at (30,13): 0.21
Setting (30,13) to 470.11
New value at (30,13): 470.11
MyException, reason: This is only a test exception, no harm done :-)
done.
```





# 5 Maven

## 5.1 Maven Central

JacORB is now available in Maven Central under the following GAVs (Group-Artifact-Version):

- Group: `org.jacorb`
- Artifacts:
  - `jacorb`
  - `jacorb-omgapi`
  - `jacorb-idl-compiler`
  - `jacorb-parent`
  - `jacorb-services`

The current version is 3.6.

## 5.2 Maven Demo

An example is supplied in `<install>/demo/maven` in order to demonstrate the use of Maven to download the JacORB artifacts, use the IDL compiler plugin and finally executing the resulting client/server. The following will describe the steps in detail.

### IDL Compiler

Before the main source files can be compiled the IDL must be generated. To do this an external plugin is used. The GAV for this plugin is:

- `org.codehaus.mojo.idlj-maven-plugin:1.2.1`

and is documented here <http://mojo.codehaus.org/idlj-maven-plugin>. Note to correctly configure the plugin the type of IDL compiler must be configured and a dependency upon the correct version of the JacORB IDL compiler added e.g.

```
<plugin>
```

```
...
```

```
<configuration>
  <compiler>jacorb</compiler>
</configuration>
<dependencies>
  <dependency>
    <groupId>org.jacorb</groupId>
    <artifactId>jacorb-idl-compiler</artifactId>
    <version>${version.jacorb}</version>
    <scope>compile</scope>
  </dependency>
</dependencies>
</plugin>
```

## Compiling

Assuming the correct JacORB dependency has been added to the Maven POM the default Maven lifecycle will build both the generated sources and the supplied sources during the 'compile' phase.

```
<dependencies>
  <dependency>
    <groupId>org.jacorb</groupId>
    <artifactId>jacorb</artifactId>
    <version>${version.jacorb}</version>
  </dependency>
</dependencies>
```

**Note:** The JacORB core and services have a transient dependency on the OMG API stubs:

```
<dependencies>
  <dependency>
    <groupId>org.jacorb</groupId>
    <artifactId>jacorb-omgapi</artifactId>
    <version>${version.jacorb}</version>
  </dependency>
</dependencies>
```

This may need to be explicitly added to the compile / exec Xbootclasspath's if you wish to use JacORB's OMG stubs.

## 6 The JacORB Name Service

Name servers are used to locate objects using a human-readable reference (their name) rather than a machine or network address. If objects providing a certain service are looked up using the service name, their clients are decoupled from the actual locations of the objects that provide this service. The binding from name to service can be changed without the clients needing to know.

JacORB provides an implementation of the OMG's Interoperable Naming Service (INS) which supports binding names to object references and to lookup object references using these names. It also allows clients to easily convert names to strings and vice versa. The JacORB name service comprises two components: the name server program, and a set of interfaces and classes used to access the service.

One word of caution about using JDK 1.2 with the JacORB naming service: JDK 1.2 comes with a couple of outdated and apparently buggy naming service classes that do not work properly with JacORB. To avoid having these classes loaded and used inadvertently, please make sure that you always use the `NamingContextExt` interface rather than the plain `NamingContext` interface in your code. Otherwise, you will see your application receive null pointer or other exceptions.

### 6.1 Running the Name Server

The JacORB name server is a process that needs to be started before the name service can be accessed by programs. Starting the name server is done by typing on the command line either simply

```
$ ns [-Djacorb.naming.ior_filename=<filename>] [-DOAPort=port]
[-Djacorb.naming.time_out=<timeout>]
```

You can also start the Java interpreter explicitly by typing

```
$ jaco jacob.naming.NameServer [-Djacorb.naming.ior_filename=<filename>]
[-DOAPort=port] [-Djacorb.naming.time_out=<timeout>]
```

In the example

```
$ ns -Djacorb.naming.ior_filename=/home/me/public_html/NS.Ref
```

we direct the name server process to write location information (its own object reference) to the file `/home/me/public_html/NS.Ref`. A client-side ORB uses this file to locate the name server process. The client-side ORB does not, however, need to be able to access the file through a local or shared file system because the file is read as a resource by using a URL pointing to it. This implies that the name server log file is accessible through a URL in the first place, i.e., that you know of a web server in your domain which can answer HTTP request to read the file.

The advantage of this approach is that clients do not need to rely on a hard-coded well known port and

that the name server is immediately available world-wide if the URL uses HTTP. If you want to restrict name server visibility to your domain (assuming that the log file is on a shared file system accessible throughout your domain) or you do not have access to a web server, you can use file URLs rather than HTTP URLs, i.e. the URL pointing to your name server log file would look like

```
file:/home/brose/public_html/NS_Ref
```

rather than

```
http://www.inf.fu-berlin.de/~brose/NS_Ref
```

Specifying file URLs is also useful if clients and servers are run on a single machine that may have no network connection at all. Please note that the overhead of using HTTP is only incurred once — when the clients first locate the name server. Subsequent requests will use standard CORBA operation invocations which means they will be IIOP requests (over TCP). In JacORB 1.4, the file name argument was made optional because the JacORB 1.4 name server also answers requests that are made using simplified corbaloc: URLs of the form `corbaloc::ip-address:port/NameService`. This means that all you need to know to construct an object reference to your name service is the IP address of the machine and the port number the server process is listening on (the one specified using `-DOAPort=<port>`).

The name server stores its internal state, i.e., the name bindings in its context, in files in the current directory unless the property `jacorb.naming.db_dir` is set to a different directory name. This saving is done when the server goes down regularly, i.e. killing the server with CTRL-C will result in loss of data. The server will restore state from its files if any files exist and are non-empty.

The second parameter is a port number on which you want the name service to listen for incoming requests. If this parameter is not set, the name server will come up on the first free port it is provided with by the operating system. The port number can also be set using specific properties in the properties file, but the `-DOAPort=;port;` switch was added merely for convenience.

The last parameter is a time-out value in msecs. If this value is set, the name server will shut down after the specified amount of time and save its state. This is useful if the name server is registered with the Implementation Repository and can thus be restarted on demand.

## Configuring a Default Context

Configuring a naming context (i.e. a name server) as the ORB's default or root context is done by simply writing the URL that points to this server's bootstrap file to the properties file `.jacorb_properties`. Alternatively, you can set this file name in the property `ORBInitRef.NameService` either on the command line or within the application as described in 2.2. After the default context has thus been configured, all operations on the `NamingContextExt` object that was retrieved by a call to `orb.resolve_initial_references("NameService")` will go to that server — provided it's running or can be started using the Implementation Repository.

## 6.2 Accessing the Name Service

The JacORB name service is accessed using the standard CORBA defined interface:

```
// get a reference to the naming service
ORB orb = ORB.init(args, null);
org.omg.CORBA.Object o = orb.resolve_initial_references("NameService")
NamingContextExt nc = NamingContextExtHelper.narrow( o );

// look up an object
server s = serverHelper.narrow( nc.resolve(nc.to_name("server.service")) );
```

Before an object can be looked up, you need a reference to the ORB's name service. The standard way of obtaining this reference is to call `orb.resolve_initial_references("NameService")`. In calls using the standard, extended name service interface, object names are represented as arrays of `NameComponents` rather than as strings in order to allow for structured names. Therefore, you have to construct such an array and specify that the name's name is "server" and that it is of kind "service" (rather than "context"). Alternatively, you can convert a string "server.service" to a name by calling the `NamingContextExt` interface's `to_name()` operation, as shown above.

Now, we can look up the object by calling `resolve()` on the naming context, supplying the array as an argument.

## 6.3 Constructing Hierarchies of Name Spaces

Like directories in a file system, name spaces or contexts can contain other contexts to allow hierarchical structuring instead of a simple flat name space. The components of a structured name for an object thus form a path of names, with the innermost name space directly containing the name binding for the object. This can very easily be done using `NameManager` but can also be explicitly coded.

A new naming context within an enclosing context can be created using either `new_context()` or `bind_new_context()`. The following code snippet requests a naming context to create an inner or subcontext using a given name and return a reference to it:

```
// get a reference to the naming service
ORB orb = ORB.init();
org.omg.CORBA.Object o =
    orb.resolve_initial_references("NameService");
NamingContextExt rootContext =
    NamingContextExtHelper.narrow( o );

// look up an object
NameComponent[] name = new NameComponent[1];
name[0] = new NameComponent("sub", "context");
NamingContextExt subContext =
    NamingContextExtHelper.narrow( rootContext.bind_new_context( name ) );
```

Please note that the JacORB naming service always uses `NamingContextExt` objects internally, even if the operation signature indicates `NamingContext` objects. This is necessary because of the limitations with JDK 1.2 as explained at the beginning of this section.

## 6.4 NameManager — A simple GUI front-end to the Naming Service

The graphical front-end to the name service can be started by calling

```
$ nmg
```

The GUI front-end will simply look up the default context and display its contents. Figure 6.1 gives a screen shot.




Figure 6.1: NameManager Screenshot

NameManager has menus that let you bind and unbind names, and create or delete naming contexts within the root context. Creating a nested name space, e.g., can be done by selecting the `RootContext` and bringing up a context by clicking the right mouse button. After selecting “new context” from that menu, you will be prompted to enter a name for the new, nested context.

# 7 The server side: POA, Threads

This chapter describes the facilities offered by JacORB for controlling how servers are started and executed. These include an activation daemon, the Portable Object Adapter (POA), and threading.

This chapter gives only a very superficial introduction to the POA. A thorough explanation of how the POA can be used in different settings and of the different policies and strategies it offers is beyond our scope here, but can be found in [?]. Other references that explain the POA are [?, ?]. More in-depth treatment in C++ can be found in the various C++-Report Columns on the POA by Doug Schmidt and Steve Vinoski. These articles are available at <http://www.cs.wustl.edu/schmidt/report-doc.html>. The ultimate reference, of course, is the CORBA specification.

## 7.1 POA

The POA provides a comprehensive set of interfaces for managing object references and servants. The code written using the POA interfaces is now portable across ORB implementations and has the same semantics in every ORB that is compliant to CORBA 2.2 or above.

The POA defines standard interfaces to do the following:

- Map an object reference to a servant that implements that object
- Allow transparent activation of objects
- Associate policy information with objects
- Make a CORBA object persistent over several server process lifetimes

In the POA specification, the use of pseudo-IDL has been deprecated in favor of an approach that uses ordinary IDL, which is mapped into programming languages using the standard language mappings, but which is locality constrained. This means that references to objects of these types may not be passed outside of a server's address space. The POA interface itself is one example of a locality-constrained interface.

The object adapter is that part of CORBA that is responsible for creating CORBA objects and object references and — with a little help from skeletons — dispatching operation requests to actual object implementations. In cooperation with the Implementation Repository it can also activate objects, i.e. start processes with programs that provide implementations for CORBA objects.

## 7.2 Threads

JacORB currently offers one server-side thread model. The POA responsible for a given request will obtain a request processor thread from a central thread pool. The pool has a certain size which is always between the maximum and minimum value configured by setting the properties `jacorb.poa.thread_pool_max` and `jacorb.poa.thread_pool_min`.

When a request arrives and the pool is found to contain no threads because all existing threads are active, new threads may be started until the total number of threads reaches `jacorb.poa.thread_pool_max`. Otherwise, request processing is blocked until a thread is returned to the pool. Upon returning threads that have finished processing a request to the pool, it must be decided whether the thread should actually remain in the pool or be destroyed. If the current pool size is above the minimum, a processor thread will not be returned into the pool again. Thus, the pool size always oscillates between max and min.

Setting `min` to a value greater than one means keeping a certain number of threads ready to service incoming requests without delay. As the threadpool can expand up to the max this is especially useful if you know that requests are likely to come in in a bursty fashion. Limiting the pool size to a certain maximum is done to prevent servers from occupying all available resources. Setting `min` to equals `max` prevents the oscillation in the size of the pool and the destruction/creation of threads.

Request processor threads usually run at the highest thread priority. It is possible to influence thread priorities by setting the property `jacorb.poa.thread_priority` to a value between Java's `Thread.MIN_PRIORITY` and `Thread.MAX_PRIORITY`. If the configured priority value is invalid JacORB will assign maximum priority to request processing threads.



# 8 Implementation Repository

“... it is very easy to be blinded to the essential uselessness of them by the sense of achievement you get from getting it to work at all. In other words — and that is a rock-solid principle on which the whole of the Corporation’s Galaxywide success is founded — their fundamental design flaws are completely hidden by their superficial design flaws.”

D. Adams: So Long and Thanks for all the Fish

The Implementation Repository is not, as its name suggests, a database of implementations. Rather, it contains information about where requests to specific CORBA objects have to be redirected and how implementations can be transparently instantiated if, for a given request to an object, none is reachable. “Instantiating an implementation” means starting a server program that hosts the target object. In this chapter we give a brief overview and a short introduction on how to use the Implementation Repository. For more details please see [?].

## 8.1 Overview

Basically, the Implementation Repository (ImR) is an indirection for requests using persistent object references. A persistent object reference is one that was created by a POA with a PERSISTENT lifespan policy. This means that the lifetime of the object is longer than that of its creating POA. Using the Implementation Repository for objects the lifetime of which does not exceed the life time of its POA does not make sense as the main function of the Implementation Repository is to take care that such a process exists when requests are made — and to start one if necessary.

To fulfill this function, the ImR has to be involved in every request to “persistent objects”. This is achieved by rewriting persistent object references to contain not the address of its server process but the address of the ImR. Thus, requests will initially reach the ImR and not the actual server — which may not exist at the time of the request. If such a request arrives at the ImR, it looks up the server information in its internal tables to determine if the target object is reachable or not. In the latter case, the ImR has to have information about how an appropriate server process can be started. After starting this server, the client receives a LOCATION\_FORWARD exception from the ImR. This exception, which contains a new object reference to the actual server process now, is handled by its runtime system transparently. As a result, the client will automatically reissue its request using the new reference, now addressing the target directly.

Beside the traditional JacORB ImR, the TAO ImR is also available as an alternative strategy for Implementation Repository in an operational environment where both TAO and JacORB service implementations co-exist. In such an environment, the TAO ImR offers an alternative approach to manage both JacORB and TAO service implementations. Please consult the chapter TAO Implementation Repository (9) for details about the TAO Implementation Repository.

## 8.2 Using the JacORB Implementation Repository

The JacORB Implementation Repository consists of two separate components: a repository process which need only exist once in a domain, and process startup daemons, which must be present on every host that is to start processes. Note that none of this machinery is necessary for processes that host objects with a TRANSIENT life time, such as used by the RootPOA.

First of all, the central repository process (which we will call ImR in the following) must be started:

```
$ imr [-n] [-p <port>] [-i <ior_file>] [-f <file>] [-b <file>] [-a]
```

The ImR is located using the configuration property `ORBInitRef.ImplementationRepository`. This property must be set such that a http connection can be made and the ImR's IOR can be read. Next, startup daemons must be created on selected hosts. To do this, the following command must be issued on each host:

```
$ imr_ssd
```

When a startup daemon is created, it contacts the central ImR.

To register a program such that the ImR can start it, the following command is used (on any machine that can reach the ImR):

```
$ imr_mg add "AServerName" -c "jaco MyServer"
```

The `imr_mg` command is the generic way of telling the ImR to do something. It needs another command parameter, such as `add` in this case. To add a server to the ImR, an implementation name is needed. Here, it is `"AServerName"`. If the host where the server should be restarted is not the local one, use the `-h hostname` option. Finally, the ImR needs to know how to start the server. The string `"jaco MyServer"` tells it how. The format of this string is simply such that the server daemon can execute it (using the Java API call `exec()`), i.e. it must be intelligible to the target host's operating system. For a Windows machine, this could, e.g. be `"start jaco MyServer"` to have the server run in its own terminal window, under Unix the same can be achieved with `"xterm -e jaco MyServer"`.

The startup command is a string that is passed as the single argument to `javas Runtime.exec()` method, without interpreting it or adding anything. Since `Runtime.exec()` has system-dependent behaviour, the startup string has to reflect that. While for most unix systems it is sufficient to avoid shell-expansions like `*` and `~`, windows-based systems do not pass the string to a commandline interpreter so a simple `jaco MyServer` will fail even if it works if directly typed in at the dos prompt. Therefore you have to "wrap" the core startup command in a call to a commandline interpreter. On NT the following startup command will do the job: `cmd /c "jaco MyServer"`. Please keep in mind that if you use the `imr_mg` command to set the startup command, you have to escape the quotes so they appear inside of the resulting string.

If you don't intend to have your server automatically started by the ImR you can also set the property `"jacorb.imr.allow_auto_register"` or use the `-a` switch of the ImR process. If this property is set, the ImR will automatically create a new entry for a server on POA activation, if the server has not been registered previously. In this case you don't have to use the ImR Manager to register your server.

For a client program to be able to issue requests, it needs an object reference. Up to this point, we haven't said anything about how persistent object references come into existence. Reference creation

happens as usual, i.e. in the server application one of the respective operations on a POA is called. For a reference to be created as “persistent”, the POA must have been created with a PERSISTENT lifespan policy. This is done as in the following code snippet:

```
/* init ORB and root POA */
orb = org.omg.CORBA.ORB.init(args, props);
org.omg.PortableServer.POA rootPOA =
    org.omg.PortableServer.POAHelper.narrow(
        orb.resolve_initial_references("RootPOA"));

/* create policies */

org.omg.CORBA.Policy [] policies = new org.omg.CORBA.Policy[2];
policies[0] = rootPOA.create_id_assignment_policy(
    IdAssignmentPolicyValue.USER_ID);
policies[1] = rootPOA.create_lifespan_policy(
    LifespanPolicyValue.PERSISTENT);

/* create POA */

POA myPOA = rootPOA.create_POA("XYZPOA",
    rootPOA.the_POAManager(), policies);

/* activate POAs */
poa.the_POAManager().activate();
```

(Note that in general the id assignment policy will be USER\_ID for a POA with persistent object references because this id will often be a key into a database where the object state is stored). If a POA is created with this lifespan policy and the ORB property “use\_imr” is set, the ORB will try to notify the ImR about this fact so the ImR knows it doesn’t need to start a new process for requests that target objects on this POA. To set the ORB policy, simply set the property `jacorb.use_imr=on`. The ORB uses another property, `jacorb.implname`, as a parameter for the notification, i.e. it tells the ImR that a process using this property’s value as its implementation name is present. If the server is registered with the ImR, this property value has to match the implementation name that is used when registering.

The application can set these properties on the command line using `java -Djacorb.implname=MyName`, or in the code like this:

```
/* create and set properties */
java.util.Properties props = new java.util.Properties();
props.setProperty("jacorb.use_imr", "on");
props.setProperty("jacorb.implname", "MyName");

/* init ORB */
orb = org.omg.CORBA.ORB.init(args, props);
```

There are a few things you have to consider especially when restoring object state at startup time or saving the state of your objects on shutdown. It is important that, at startup time, object initialization is complete when the object is activated because from this instant on operation calls may come in. The repository knows about the server when the first POA with a PERSISTENT lifespan policy registers, but does not forward object references to clients before the object is actually reachable. (Another, unreliable way to handle this problem is to increase the `jacorb.imr.object_activation_sleep` property, so the repository waits longer for the object to become ready again.)

When the server shuts down, it is equally important that object state is saved by the time the last POA in the server goes down because from this moment the Implementation Repository regards the server as down and will start a new one upon requests. Thus, a server implementor is responsible for avoiding reader/writer problems between servers trying to store and restore the object state. (One way of doing this is to use POA managers to set a POA to holding while saving state and to inactive when done.)

Please keep in mind that even if you don't have to save the state of your objects on server shutdown you must deactivate your POAs prior to exiting your process (or at least use `orb.shutdown(...)` which includes POA deactivation). Otherwise the ImR keeps the server as active and will return invalid IORs. In case of a server crash you can either notify the ImR manually by using the command `imr_mg setdown AServerName` or allow the ImR to detect the crashed server and restart it if necessary.

## 8.3 Server migration

The implementation repository offers another useful possibility: server migration. Imagine the following scenario: You have written your server with persistent POAs, but after a certain time your machine seems to be too slow to serve all those incoming requests. Migrating your server to a more powerful machine is the obvious solution. Using the implementation repository, client references do not contain addressing information for the slow machine, so server migration can be done transparently to client.

Assuming that you added your server to the repository, and it is running correctly.

```
$ imr_mg add AServerName -h a_slow_machine -c "jaco MyServer"
```

The first step is to hold the server, that means the repository delays all requests for that server until it is released again.

```
$ imr_mg hold AServerName
```

Now your server will not receive any requests for its registered POAs. If you can't shut your server down such that it sets itself down at the repository, i.e. your POAs are set to inactive prior to terminating the process, you can use

```
$ imr_mg setdown AServerName
```

to do that. Otherwise your POAs can't be reactivated at the repository because they are still logged as active.

If you want your server to be restarted automatically, you have to tell the repository the new host and maybe a new startup command.

```
$ imr_mg edit AServerName -h the_fastest_available_machine
```

```
-c "jaco MyServer"
```

If your server can be restarted automatically, you now don't even have to start it manually, but it is instead restarted by the next incoming request. Otherwise start it manually on the desired machine now.

The last step is to release the server, i.e. let all delayed requests continue.

```
$ imr_mg release AServerName
```

By now your server should be running on another machine, without the clients noticing.

## 8.4 A Note About Security

Using the imr can pose a major security threat to your system. Imagine the following standard setup: an imr is running on a machine, its IOR file is placed in a directory where it can be read by the web server, and several imr\_ssds are running on other machines. An attacker can now execute processes on the machines the ssds are running on by taking the following steps:

1. Setting the `ORBInitRef.ImplementationRepository` property to the IOR file on your server.
2. Creating a new logical server with the desired command to execute as startup command on the desired host (where a ssd is running). This is the crucial point. The ssd calls `Runtime.exec()` with the supplied string, and there is no way to check if the command does what it is supposed to do, i.e. start a server.
3. Start the server with the `imr_mg`. The startup command of the server will be exec'd on the specified host.

Now this should not generally discourage you to use the imr but show you that there are risks, which can be reduced significantly nonetheless. There are several ways to encounter this threat and we don't consider this list to be complete:

1. Try to control the distribution of the IOR file. Hiding it should not be considered here, because *security by obscurity* is generally a bad approach. Try to make use of file system mechanisms like groups and ACLs.
2. Use a firewall which blocks incoming traffic. Keep in mind that if the attacker is inside of your protection domain, the firewall won't help. It is also not that hard to write a Trojan that can tunnel those firewalls that block incoming traffic.
3. Enforce SSL connections to the imr. This blocks all client connections that don't have a certificate signed by a CA of your choice. See chapter 13 for more information.



# 9 TAO Implementation Repository

The information presented in this chapter is borrowed from the Object Computing Inc.'s TAO Developer's Guide. Please visit <http://www.theaceorb.com/product/index.html> for more details.

## 9.1 Introduction

In an homogeneous CORBA environment, the obvious choice for the Implementation Repository is by using the native implementation repository service, so logically, the JacORB ImR would be selected for managing JacORB servers and likewise for others such as TAO; however, this arrangement would become cumbersome in an environment where both JacORB and TAO servers coexist. In such an environment, the TAO ImR would offer an alternative choice for the Implementation Repository because it is capable of managing both JacORB and TAO servers. As with using a JacORB ImR, the interactions with using the TAO ImR is transparently to the client requests for services from the servers.

The TAO Implementation Repository (ImR) is written in C++, and like the JacORB ImR, is a service which allows indirect invocation of CORBA operations. Instead of connecting to a server, clients initially connect to the ImR. The ImR will then optionally start the appropriate server if the server is not running, and then provide the address of the server to the client so that subsequent requests will go to this server.

Indirectly binding with the server in this manner can be useful in minimizing the changes needed to accommodate server or object migration, allow for automatic server start-up, and help in load balancing. When using indirect binding, the ImR address is substituted for the actual server address in the IOR. When the ImR receives a client request it extracts the POA name from the object key, and uses it to find a matching registered server IOR. The ImR then responds with a `LOCATION_FORWARD` message which instructs the client to repeat the request using the new IOR. Subsequent client requests using the same object reference continue to use the established server connection, and the ImR is not involved. Please note that it is possible for a client to create another connection. For example, upon receiving a `COMM_FAILURE` exception, a client may decide to retry by invoking the operation again. The ImR will again forward the client to the registered server if possible.

Throughout this chapter, a POA that uses a `PERSISTENT` lifespan policy and a `USER_ID` object id assignment policy is referred to as a persistent POA, and an object that is registered with a persistent POA is referred to as a persistent object. Frequently the terms POA and server are used interchangeably, because the ImR treats each registered POA as a separate server. However, each server is capable of hosting multiple persistent POAs, each of which may contain multiple indirect object references.

The ImR supports the ability to launch server processes on demand. Without the ImR, all servers must be running prior to any client request. This can result in performance problems, especially for large

systems, since servers consume system resources even in their idle states.

## 9.2 The Operation of the TAO ImR

The TAO ImR requires that an IOR it works with live beyond the server that created the IOR. Therefore, the IOR must be created using a POA with the `PERSISTENT` life span policy. If a JacORB servers ORB was initialized by setting the property `jacorb.use_tao_imr` to on, then the persistent POA registers itself, upon creation, with the ImR. If a JacORB server has more than one persistent POA, each is registered as a separate server within the ImR. For each persistent POA, the following information is registered:

- Server Name which has the form `JACORB:implname qualified POA name`.
- Address which is in URL format. (e.g., `corbaloc:iiop:1.2@127.0.0.1:8888/`)
- `ServerObject` which is a simple call-back object, that the ImR would invoke to ping and shut-down the associated server.

Please note that in order for a JacORB server to locate the ImR, the configuration property `ORBInitRef.ImplRepoService` must be set to the ImR's IOR reference either in a property file, or as a passed-in command-line property.

In addition, the ImR Utility `tao_imr` can be used to register the following parameters for a registered server:

- Activation mode which defines the condition to start/restart the server.
- Start-up command which is used to start/restart the server.
- Environment variables which defines the operating environment for the server.
- Working directory which specifies the directory where the server is to be started/restarted.
- Start retry limit which specifies the number of attempts in trying to start/restart the server.

These parameters are needed in order for the ImR to start/restart a register server when its services are demanded by the clients. If none was registered, the ImR will take no action on a register server which could cause the client to receive a `TRANSIENT` exception while attempting to re-establish conversation with the targeted server.

## 9.3 Using the TAO Implementation Repository

The ImR consists of the following components:

- The ImR Locator `tao_imr_locator` which is generally referred to as the Implementation Repository. It needs only exist once in a domain. The full path to the `tao_imr_locator` is `$TAO_ROOT/orbsvcs/ImplRepo-Service/tao_imr_locator`.
- The ImR Activator `tao_imr_activator` which is a simple process-starting service that accepts start-up information for a registered server from the ImR



and attempts to launch the server. The full path to the `tao_imr_activator` is `$TAO_ROOT/orbsvcs/ImplRepo_Service/tao_imr_activator`.

- The ImR Utility `tao_imr` which is an interactive process that is used to perform administrative tasks. The full path to the `tao_imr` is `$TAO_ROOT/orbsvcs/ImplRepo_Service/tao_imr`.

### 9.3.1 Server Requirements

In order for persistent POAs to be registered with the ImR upon POA creation, the following properties must be set as indicated:

- `jacorb.use_tao_imr` must be set to on.
- `jacorb.use_imr` must be set to off. An exception will be thrown if both properties above were found to be set to on.
- `jacorb.implname` must be set.
- the configuration property `ORBInitRef.ImplRepoService` must be set to the IOR of the targeted ImR either in a property file, or as a passed-in command-line property.

### 9.3.2 Client Requirements

In order for a client to request services from a registered server through the ImR, the following properties must be set as indicated:

- `jacorb.use_tao_imr` must be set to on.
- `jacorb.use_imr` must be set to off. An exception will be thrown if both properties are set to on.
- The server's ImR-ified IOR must be used for requesting services.

The typical process to integrate a JacORB server with a ImR so that the server will be automatically started and restarted comprises of the following steps:

1. Setup JacORB and TAO environment variables
2. Initiate the ImR Locator `tao_imr_locator`.
3. Initiate the ImR Activator `tao_imr_activator`.
4. Register the JacORB server with the ImR using the `add` command of the ImR Utility `tao_imr`.
5. Initiate JacORB clients using the server's ImR-ified IOR references which will cause the target server to be initiated by the ImR Activator.

In the following subsequent sections, we will exam each step in the above process. For illustration, we will use the ImR integration test package `org.jacorb.test.orbreinvoke.tao_imr` whose source files and test scripts are kept in the directory `$JACORB_HOME/test/orbreinvoke/tao_imr`.

### 9.3.3 Environment Variables

Before initiating the ImR processes, the following JacORB and TAO environment variables must be setup:

- JACORB\_HOME and properties file
- ACE\_ROOT and TAO\_ROOT
- PATH=\$PATH:\$ACE\_ROOT/bin
- LD\_LIBRARY\_PATH=\$ACE\_ROOT/lib
- LD\_LIBRARY\_PATH=\$ACE\_ROOT/lib (needed for MACOS)

There are helper scripts in the `$JACORB_HOME/test/orbreinvoke/tao_imr` that you can run as they will be pointed out while following the discussion. In order to run the scripts on a UNIX/LINUX system, you would need to change directory to the said directory. In addition, you can consult the README file in the said directory for concise instructions of how to run the scripts.

### 9.3.4 Initiate The TAO ImR Locator `tao_imr_locator`

Assuming that we have a fictitious ImR to be used in our domain, then the first process that must be started is the Tao ImR Locator by running:

```
$ $TAO_ROOT/orbsvcs/ImplRepoService/tao_imr_locator
-ORBListenEndpoints iiop://<host>:<port> -d 2 -m 1 -t 120 -x
/tmp/tao_imr_locator.persistent.xml -o /tmp/tao_imr_locator.ior
```

For illustration, you can run the script :

```
$ ./run_tao_imr_locator.sh.
```

where the arguments are:

- `-ORBListenEndpoints iiop://<host>:<port>` specifies the endpoint.
- `-d 2` means setting debug level 2.
- `-m 1` means enabling multicast IOR discovery.
- `-t 120` means setting imeout to120 seconds.
- `-x /tmp/tao_imr_locator.persistent.xml` means using XML persistent file.
- `-o /tmp/tao_imr_locator.ior` means outputting the IOR to a file.

Normally, the ImR can be located using the configuration property `ORBInitRef.ImplRepoService`. For example,

```
$ ORBInitRef ImplRepoService=file:///tmp/tao_imr_locator.ior
```

however, for the ImR Activator and ImR Utility, they can also locate the ImR by querying the environment variable `ImplRepoServiceIOR`. For example,

```
$ export ImplRepoServiceIOR=file:///tmp/tao_imr_locator.ior
```

### 9.3.5 Initiate The TAO ImR Activator

For our fictitious ImR, assuming that we have a JacORB server residing on a host named `myhost.ociweb.com` that is to be automatically started/restarted, then the ImR Activator is the next process that must be started on `myhost.ociweb.com` by running:

```
export ImplRepoServiceIOR=///tmp/tao_imr_locator.ior
$TAO\_ROOT/orbsvcs/ImplRepo_Service/tao_imr_activator \
    -d 2 -n <myhost.ociweb.com> -o /tmp/tao_imr_activator.ior
```

For illustration, you can run the script:

```
$ ./run_tao_imr_activator.sh.
```

where the arguments are:

- `-d 2` means setting debug level 2.
- `-n <myhost.ociweb.com>` means setting the name of the Activator to `myhost.ociweb.com`.
- `-o /tmp/tao_imr_activator.ior` means outputting the IOR to a file.

Upon initiated, the Activator will locate the ImR using the environment variable `ImplRepoServiceIOR` and register itself to the ImR. Please refer to the `tao_imr_activator` section for more details.

### 9.3.6 Register the JacORB server

Once the Locator and the Activator are running, the JacORB server on `myhost.ociweb.com` must be registered with the ImR by using the `add` command of the ImR Utility `tao_imr` as following:

```
export ImplRepoServiceIOR=///tmp/tao_imr_locator.ior
$TAO\_ROOT/orbsvcs/ImplRepo\_Service/tao\_imr \
    {\tt add JACORB:<implname>/<qualified POA name>} \
    < . . . other arguments . . .>
```

Note: for illustration, you can run the script `./tao_imr_add.SimpleServer.sh` as following:

```
$ ./tao_imr_add.SimpleServer.sh EchoServer1
```

which essentially invokes the `tao_imr` utility to add an entry to the ImR repository as follows:

```
export ImplRepoServiceIOR=///tmp/tao_imr_locator.ior
$TAO\_ROOT/orbsvcs/ImplRepo_Service/tao_imr \
    add JACORB:EchoServer1/EchoServer-POA \
    -a NORMAL \
    -e ImplRepoServiceIOR=file:///tmp/tao_imr_locator.ior \
```

```

-e JACORB_HOME=${JACORB_HOME} \
-e ACE_ROOT=${ACE_ROOT} \
-e TAO_ROOT=${TAO_ROOT} \
-e LD_LIBRARY_PATH=${ACE_ROOT}/lib \
-e LD_LIBRARY_PATH=${ACE_ROOT}/lib \
-e PATH=${JACORB_HOME}/bin:${ACE_ROOT}/bin:${TAO_ROOT}/bin:${PAT
-w ${JACORB_HOME}/test/orbreinvoke/tao_imr \
-r 3 \
-l myhost.ociweb.com} \
-c <command line arguments to initiate the server process named
{\tt org.jacorb.test.orbreinvoke.tao_imr.SimpleServer}>

```

where the argument are:

- add `JACORB:EchoServer1/EchoServer-POA` means adding a JacORB server whose `implname` is `EchoServer1` and whose `POA` name is `EchoServer-POA`.
- `-a NORMAL` means the server will be initiated using `NORMAL` mode of activation. Other activation mode is `PER_CLIENT`.
- `-e environment variable=value;` means setting the specified environment variable to the desired value.
- `-w $JACORB_HOME/test/orbreinvoke/tao_imr` means setting the directory where the server will be initiated from.
- `-l myhost.ociweb.com` means setting the Activator name.
- `-c command line arguments to initiate the server` means setting the command line arguments that are needed for the server to be started or restarted by the ImR Activator.

If successfully registered, you should see the response `Successfully registered <JACORB:EchoServer1/EchoServer-POA>`.

To review the entry in the ImR repository , you can run:

```

export ImplRepoServiceIOR=///tmp/tao_imr_locator.ior
$TAO_ROOT/orbsvcs/ImplRepo_Service/tao_imr list -v

```

or, you can run the script `./tao_imr.sh list -v`, which essentially a wrapper script that invokes the `list -v` command of the `tao_imr` utility,

You should see an entry that is similar to that shown below:

```

Server <JACORB:EchoServer1/EchoServer-POA>
Activator: - - -
Command Line: - - -
Working Directory: - - -
Activation Mode: - - -
( . . . other parameters . . . )
Not currently running

```

### 9.3.7 Server Start-up

The exact conditions under which the ImR decides to start a server are determined by the Activation Mode described below, but typically the ImR starts a server if it is not registered as running, or if the server cannot be pinged successfully. Once the server has been started, the ImR waits for the server to register its running information, which includes a `ServerObject` and a partial IOR. Multiple simultaneous client invocations are supported, and each blocks, waiting on the server to register this information. Each persistent POA in the server is treated as a separate server registration within the ImR, and currently this registration happens as soon as the POA is created.

In the future this registration may be delayed until the POA Manager is activated. This would prevent problems with servers notifying the ImR before they are actually ready to handle requests.

Once the server registers its running information, the ImR wakes one of the waiting client operations, and uses it to ping the server to ensure that it is really running. The result of the ping determines whether the server is running, not running, or is in an indeterminate state.

**Running** If the server is running, or if the start-up retry count has been exceeded, then all clients are awakened and forwarded to the server. By connecting the clients to the server if the retry count was exceeded the clients can get the appropriate error status directly from the server.

**Not Running** If the server is not running, then the whole start-up process is repeated if a start-up retry count is configured for the server.

**Indeterminate** If the status cannot be determined, the ping repeats a fixed number of times with an increasing delay between subsequent attempts. To more efficiently handle multiple client requests, the `ping()` operation has a defined interval that is passed to the ImR at start-up. If a ping has successfully completed within the specified interval, then the server is assumed to be running.

The `ping()` operation has a very short timeout configured, and a timeout is considered proof that the server is running. A well-written server should avoid activating the POA Manager until the server is actually ready to handle requests.

In some instances, a server may not register its running status with the ImR within the allowed start-up time. (See the `t` command line option for the ImR.) This is treated as a start-up failure, and start-up may be retried as described previously.

If the start-up retry count is exceeded then a server becomes locked, and the ImR will not attempt to start that server again. Instead it immediately returns a `TRANSIENT` exception to any waiting clients. You can reset the start-up retry count using the `tao.imr` utility.

If a server dies unexpectedly while communicating with a client, then the client may get a `COMM.FAILURE` exception. If the client simply reattempts the operation, then it is once again directed through the ImR, which may allow the ImR to restart the server. However, if the server was pinged successfully within the configured ping interval, then the client may be redirected to the dead server, and receive a `TRANSIENT`.

## Activation Modes

The ImR supports registering servers with one of four different activation modes. These affect how a server is started, and have no meaning if a server is not start-able. For a server to be start-able, it must have a registered command line and Activator name, and the corresponding Activator must be registered and running.

Note: if a server registers itself automatically then no Activator or command line will be associated.

You must configure the activation mode using the `tao_imr`'s `add/update` command. Alternatively, you may stop the ImR, edit the XML or Windows registry persistent data manually, then start the ImR to initiate the changes. The ImR has the ability to start a server on demand, at ImR start-up, or in response to commands from the `tao_imr` utility.

Valid activation modes are:

**normal** The common usage of the ImR is to have it automatically start any servers as needed for incoming client requests. This mode also allows servers to be manually started using the `tao_imr start` command.

**auto\_start** This behaves exactly like normal mode, except that the ImR attempts to start the server as the ImR itself is started. You can also use the `tao_imr autostart` command to manually start these servers.

**manual** This prevents the server from starting automatically as the result of an incoming client request. You must use the `tao_imr start` command to start the server, or start the server manually using some other mechanism.

**per\_client** The name of this mode can be misleading, because the ImR does not actually keep track of which clients have attempted to use a server. Instead this simply means that a new server will be spawned for each incoming request to the ImR. Once a client has been forwarded by the ImR to an actual server, the client will continue to use this connection for future communications until a `TRANSIENT` or `COMM.FAILURE` exception occurs. In this case, the client will make a connection back to the ImR, and the process will repeat.

It is possible for a client to make a second connection using the indirect object reference, and this will cause the ImR to launch another server. For this reason, `per_client` activation should be used with care.

### 9.3.8 Initiate the JacORB client

The server process `org.jacorb.test.orbreinvoke.tao_imr.SimpleServer`, that is associated with the registered server name `JACORB:EchoServer1/EchoServer-POA` is simply an echoing server. Upon initiated, it will instantiate an `EchoMessage` servant that is tied to the object key `/EchoServer1/EchoServer-POA/EchoServer-ID`.

To produce a partial corbaloc IOR string that can be used by a client process, you can run the script:

```
$ ./tao_imr.sh ior JACORB:EchoServer1/EchoServer-POA
```

You should see an entry that is similar to that shown below:

```
corbaloc:iiop:V.v@<ImR host>:<ImR port>/EchoServer1/EchoServer-POA
```

Thus, a client process can request the service from the EchoMessage servant of the SimpleServer through the ImR by using the following IOR:

```
corbaloc:iiop:V.v@<ImR host>:<ImR port>/EchoServer1/EchoServer-POA/EchoServer
```

For illustration, you can run the script:

```
$ ./run.SimpleClient.sh EchoServer1 [ImR hostname]
```

which will initiate the client process `org.jacorb.test.listenendpoints.echo_corbaloc.Client`. The argument `[ImR hostname]` is required if you initiate the Locator on a remote host. Upon initiation, the client process will use the described corbaloc IOR to locate the server through the ImR. Sensing requests from the client, the ImR will initiate the SimpleServer since it has not been running.

Upon successful connection to the server, the client application will keep pinging the server in a loop using sequential messages and output the result to a log file `./output/Client_nnn.log`. You can tail the log file to follow the activities.

When finished, do the following to cleanup:

- Find and kill `org.jacorb.test.listenendpoints.echo_corbaloc.Client`
- Shutdown the SimpleServer server using:
 

```
$ ./tao_imr.sh shutdown "JACORB:EchoServer1/EchoServer-POA"
```
- Shutdown the ImR Locator and Activator using:
 

```
$ ./tao_imr.sh shutdown-repo -a
```
- Remove the file `/tmp/tao_imr_locator.persistent.xml` if no longer needed.

## 9.4 Repository Persistence

The ImR can load and save its list of registered servers and Activators to persistent storage using one of three formats. The easiest to work with is an XML format that can be edited by hand. The XML file is rewritten in response to any change in registration information, and may therefore be inefficient for large, or very busy, repositories. A more efficient binary format is supported, but this can be difficult to work with, and is known to have problems on some platforms. The ImR can also save its registration information to the registry on Windows systems.

**XML** Starting the ImR with `x repo.xml` creates a file containing an entry for every registered server and Activator. The schema for this XML file can be found at `$TAO_ROOT/orbsvcs/ImplRepo_Service/ImR.xsd`.

**Binary** Starting the ImR with `p repo.bin` stores registered Activators and servers in a binary file. This option may have problems on some platforms when the memory mapped file used internally needs to be expanded.

**Windows registry** Starting the ImR with `r` stores registered servers and Activators at:

```
HKEY_LOCAL_MACHINE
SOFTWARE
TAO
ImplementationRepository.
```

## 9.5 TAO ImR Utility

TAO provides a command line tool called `tao_imr` that you can use to:

- add or edit server information in the ImR,
- create IORs suitable for connecting to a server,
- view the status of registered servers,
- start or shutdown registered servers.

### 9.5.1 Command Line Options

The general syntax for the ImR utility is:

```
$ tao_imr command [options] [args]
```

Most of the commands take a server name as an argument. You can get help information on each command via the `-h` option. For example:

```
$ tao_imr start -h
```

```
{\tt Usage: tao_imr [options] start <name> where [options] are ORB options
where <name> is the name of a registered POA. -h Displays this}
```

#### add/update

**Synopsis** `tao_imr add|update <server> [-a normal|manual|per_client|auto_start] [-c cmdline] [-e var=value] [-w working dir] [-r count] [-l activator]`

These commands are used to add a new server registration and to update an existing server registration respectively. They take exactly the same options. The only difference is that `add` cannot be used to change an existing server. This means you can use `update` to add new servers.

You may specify an activation mode of `auto_start`, `manual`, `normal`, or `per_client`. The default activation mode is `normal`.

Note: It is possible for a client to make a second connection using the indirect object reference, and this will cause the ImR to launch another server. For this reason, `per_client` activation should be used with care.



The command line, working directory, environment variables, and retry count are all optional, but you must specify at least a command line if you want the ImR to be able to start the server. The command line can be any command, and does not necessarily have to directly start the server. For example, it could run a script that causes the creation of a new persistent POA in an already running server process.

You can specify the `e` option multiple times on a single command line to set multiple environment variables. The specified environment variables will replace any that currently exist when updating.

The working directory does not affect the command line. If the command is not in the path, then specifying the working directory does not allow the command to run. Therefore, you must also specify the directory to the command line argument.

The retry count is a feature to prevent further attempts to start servers that are not functioning correctly. If a server either cannot be started by the Activator, or does not register its running information with the ImR in a timely manor, then the ImR will attempt to start it again. The start-up timeout is a command line option to the ImR that is shared by all servers. An additional feature of the update command is that it always resets the start-up count for a server.

You can specify an activator for a server, and this defaults to the hostname of the machine on which the `tao_imr` utility is run. If you use the `n name` feature of the Activator then you must use the same name here so that the ImR can find the correct Activator to start the server. Any auto-added servers will not have an Activator set, so the `tao_imr update` command must be used to set it if you want to make the server start-able.

## autostart

**Synopsis** `tao_imr autostart <server>`

This command is used to start all servers registered with the `auto_start` activation mode. In other respects it works exactly the same as the `start` command.

## ior

**Synopsis** `tao_imr autostart <server>`

This command can be used to construct a valid simple `corbaloc` URL for accessing a server registered with the ImR. This is only useful if the address of the ImR is unknown, because, for example, you are using multicast to find the ImR. If the address of the ImR is known, then it is easier to construct the URL manually using the form:

```
$ corbaloc:protocol:host_or_ip:port/ServerName
```

The `ior` command does not actually contact the ImR to lookup the address of the server. Instead it uses the first available protocol specified for the ImR connection.

## list

**Synopsis** `tao_imr list [-v]`

Use this command to view the current status of all servers registered in the ImR. You will probably want to use the verbose option `v` most of the time. All information registered using the `add/update` commands is displayed as well as the current running status of the server and whether the server is locked due to exceeding its retry count. If the server is locked, you can unlock it using the `update` command. For example:

```
$ tao_imr update myserver
```

## remove

**Synopsis** `tao_imr remove <server>`

This command simply removes all information about the server from the ImR. If the server is running it is not shut down by this command. If the server is removed without being shut down first, then a `NOT_FOUND` exception will be caught by the server when it tries to unregister from the ImR. This exception is ignored, but an error message is displayed.

subsubsectionsshutdown

**Synopsis** `tao_imr shutdown <server>`

This command shuts down a running server by using the `ServerObject` that every server internally registers with the ImR at start-up. The `orb->shutdown(0)` operation is called in the server, typically causing the server to return from `orb->run()` and shut down gracefully. Note that this means servers with multiple persistent POAs can be shut down using any one of the POA names. If this behavior is not desired, then you should use separate ORBs in the server.

## shutdown-repo

**Synopsis** `tao_imr shutdown-repo [-a]`

This command shuts down the ImR cleanly. This can also be done by using `Ctrl-C`, or sending a `SIGINT` or `SIGTERM` to the ImR and/or Activator processes. The `-a` option specifies that you also want to attempt to shut down any registered Activators. If any Activator cannot be shut down, it is ignored, and no error is returned.

## start

**Synopsis** `tao_imr start <server>`

This command This command is used to ensure that the specified server is activated, starting the server process, if necessary, using the Activator registered for the server. If the server is not already running, this requires that

1. The server has already been registered using `add` or `update`.
2. The registration information includes a command line and activator name.

### 3. A matching Activator is registered and running.

If any of the above conditions are not met, or if there is some problem activating the server, then an error message is returned.

Note 1: This command was previously named `activate`. That command name still works but displays a warning that it is deprecated. It is possible for the utility to report success when the ImR exceeds its ping retry count. In this case the server was not activated, and `list v` will show that the server is locked.

## 9.6 tao\_imr\_locator

`tao_imr_locator` is the primary application that we generally refer to as the ImR. It is responsible for maintaining a repository of server and activator information, and using it to support indirect binding of CORBA objects.

If the ImR is not started with multicast service discovery support, then you must provide some mechanism for other processes to find the ImR when they use `resolve_initial_references()`. This requires the servers, Activators, and `tao_imr` to be started with an `ORBInitRef` option, such as:

- `-ORBInitRef ImplRepoService=corbaloc::host:port/ImR`
- `-ORBInitRef ImplRepoService=corbaloc::host:port/ImplRepoService`
- `-ORBInitRef ImplRepoService=file://ImR.ior`
- `-ORBDefaultInitRef corbaloc::host:port`

Alternatively, you can set the `ImplRepoServiceIOR` environment variable:

```
$ export ImplRepoServiceIOR=corbaloc::host:port/ImR
```

For most of the above to work, the ImR must be started at a known endpoint such as:

```
$ -ORBListenEndpoints iiop://:8888 -ORBListenEndpoints
iiop://host:port.
```

The full path to the ImR is: `$TAO_ROOT/orbsvcs/ImplRepo_Service/tao_imr_locator`.

### 9.6.1 Command Line Options

**Synopsis** `tao_imr_locator [-h|-?] [-d 0|1|2] [-l] [-m] [-o filename] [-p filename] [-r] [-x filename] [-v interval] [-t timeout] [-c command]`

**Synopsis** `tao_imr_locator [-c cmd] [-d 0|1|2] [-m] [-o file]`

Table 9.1: tao\_imr\_locator Command Line Options

Option	Description
--------	-------------

Table 9.1: tao\_imr\_locator Command Line Options

Option	Description
-h or -?	Display help/usage.
-d	Specify IMR specific debugging level, 0-2. Default is 1.
-l	Lock the database to prevent tao_imr add, update, and remove.
-m	Enable support for IOR multicast to find the ImR.
-o filename	Write the ImR Administration IOR to filename.
-p filename	Use binary persistence.
-r	Use Window registry persistence.
-x filename	Use XML persistence.
-v interval	Ping interval in milliseconds. Default is 10 seconds.
-t timeout	Start-up timeout in seconds. Default is 60 seconds.
-c command	install or remove the Windows service.
-e	Erase all persistence information at start-up.
UnregisterIfAddressReused	This option causes the ImR to automatically remove a server from the implementation repository when another server is registered with the same endpoint. This option should not be used if more than one persistent POA in the same ORB is being used via the ImR.

Currently, there are three valid settings for the debug level:

- 0** Most output is disabled.
- 1** Very basic information is outputted, with usually just one line per interesting operation.
- 2** More messages and details are outputted for existing messages.

In practice, debug level 1 is probably the best choice for day-to-day usage, while level 2 is most useful when trying to resolve problems.

The `-l` option prevents the ImR repository information from being modified by the `tao_imr add` or `update` commands. However, server auto-registration, Activator registration, and server running status are all still persisted to the repository.

The `-m` option provides a convenient way for all servers and Activators to find the ImR without the need to pass IORs, use corbaloc object URLs, or use the `ORBInitRef` option. Instead, a multicast endpoint is established when the ImR starts, and servers and Activators automatically find the correct IOR using multicast. The multicast port may be specified using:

```
$ -ORBMulticastDiscoveryEndpoint <port>
```

If this option is not specified, then the environment variable `ImplRepoServicePort` is used. The default port number is 10018.

The output file for the `-o` option is a simple stringified IOR stored in a text file, suitable for use as a `file://` object URL.

The `-v` option allows the ImR to more efficiently work with servers. If the ImR has successfully pinged a server within the specified number of milliseconds, then it assumes that the server is still running. Setting the ping interval to zero disables the ping feature completely, and servers are assumed to be running if they register a running status with the ImR.

**Note:** in the current implementation for server registration, the server notifies the ImR of its running status when the persistent POA is created. As such, the ImR may sometimes forward a client to a server that is not yet ready to handle requests, thereby causing the client to receive a TRANSIENT exception indicating that the servers POA is in the holding state. The ImRs ping feature can be used to allow the ImR to ensure the server is ready to handle requests before forwarding the client to the server. If the ping feature is disabled, the application should be prepared to handle the TRANSIENT exception (e.g., by retrying the request).

The `-t` option allows the user to set a timeout value, in seconds, by which the ImR will wait before giving up on starting a server. If the ImR does not receive running information from a server within the specified timeout interval, it will abort the server start-up. Depending on the servers retry count setting, the ImR may attempt to launch the server again. Once the retry count has been exceeded, the ImR will not attempt to start the server again until an administrator uses `tao_imr update` to reset the servers start-up counter. The start-up timeout value can be disabled by specifying `t 0` when starting the ImR. However, disabling the start-up timeout is not recommended as the ImR could become blocked permanently waiting for a server to start. The default start-up timeout value is 60 seconds.

The `-UnregisterIfAddressReused` option is intended to solve a specific issue with server restarts when a group of servers, each with one persistent POA, are sharing a common set of ports via the `portspan` endpoint option. Because these servers can swap ports on a restart, the ImR needs to be able to automatically clear them out when a new server takes the port. In addition to the normal start-up options, the `c install` or `c remove` options can be used to install or remove the ImR as a Windows service. When installing, all other command line options are saved in the Windows registry under:

```
{\tt HKEY\_LOCAL\_MACHINE\\SYSTEM\\CurrentControlSet\\Services\TAOImR}
```

These options are used when the service is started.

## 9.6.2 Examples

Start the ImR with default options:

```
$ ./tao_imr_locator
```

and the outputs are:

```
Implementation Repository: Running
    PingInterval : 10000ms
    Startup Timeout : 60s
    Persistence : Disabled
    Multicast : Disabled
    Debug : 1
```

```
Locked : False
```

Start with alternative options:

```
$ ./tao.imr.locator -v 500 -t 5 -x repo.xml -m d 2 1
```

and, the output are:

```
Implementation Repository: Running
    Ping Interval : 500ms
    Startup Timeout : 5s
    Persistence : repo.xml
    Multicast : Enabled
    Debug : 2
    Locked : True
```

Install as a Windows service with several non-default options

```
$ ./tao.imr.locator v 1000 t 30 p repo.bin ORBListenEndpoints
iiop://:8888
```

```
install
```

Start a server

```
$ myserver ORBUseIMR 1 ORBInitRef ImplRepoService=file://imr.ior
```

## 9.7 tao\_imr\_activator

The Activator is an extremely simple process-starting service. It accepts start-up information from the ImR, and attempts to launch a process.

Note: On UNIX and UNIX-like platforms the Activator can detect when spawned processes terminate, and can optionally notify the ImR when this happens.

Once started, the server registers itself with the ImR directly. Each persistent POA within the server registers itself as a separate server within the ImR. The start-up information passed to the Activator does not necessarily have to directly start a server. For example, it could run a script that causes the creation of a new persistent POA in an already running server process.

At start-up, the ImR Activator tries to register itself with an ImR. If an ImR cannot be found, the Activator will not be able to notify the ImR when it is shut down or when spawned processes are terminated.

The full path to the tao\_imr\_activator is \$TAO\_ROOT/orbsvcs/ImplRepo\_Service/tao-imr-activator.

## 9.7.1 Command Line Options

**Synopsis** `tao_imr_activator [-c cmd] [-d 0|1|2] [-e buflen] [-o filename] [-l] [-n name] [-m maxenv]`

Table 9.2: tao\_imr\_activator Command Line Options

Option	Description
<code>-h</code> or <code>-?</code>	Display help/usage.
<code>-o filename</code>	Write the Activator IOR to <code>filename</code> .
<code>-n name</code>	The name of the Activator. Default is the name of the host on which the Activator is running.
<code>-l</code>	Notify the ImR when spawned processes die. (Not supported on all platforms.)
<code>-c command</code>	<code>install</code> , <code>remove</code> or <code>install_no_imr</code> the Windows service.
<code>-e buflen</code>	Sets the length in bytes of the environment buffer for activated servers. The default is 16 KB.
<code>-m maxenv</code>	Sets the maximum number of environment variables for activated servers. The default is 512.

Currently, there are three valid settings for the debug level:

- 0** Most output is disabled.
- 1** Very basic information is outputted, with usually just one line per interesting operation.
- 2** More messages and details are outputted for existing messages.

In practice, debug level 1 is probably the best choice for day-to-day usage, while level 2 is most useful when trying to resolve problems.

In practice, debug level 1 is probably the best choice for day-to-day usage, while level 2 is most useful when trying to resolve problems. The output file for the `-o` option is a simple stringified IOR stored in a text file, suitable for use as a `file://` object URL. This option is not very useful, because typically the ImR is the only client for the Activator.

You can change the name of an Activator instance, which allows running more than one Activator on a single machine. This probably is not of much practical value unless you were to create your own Activator class that behaves differently from the default simple process launching service. For example, you might create an activator that spawns servers as threads within its own process.

The `-e` and `-m` options are both configuration parameters that control size limitations of the environment passed to spawned processes. The `-e` option sets a limit for the size of the buffer (in bytes) that is used to hold the environment variables. The `-m` option sets a limit for the number of environment variables that can be passed. The default limits are 512 variables and 16 KB of buffer space. In addition to the normal start-up options, the `c install`, `-c remove`, and `c install_no_imr` options can be used to install or remove the Activator as an Windows service. When installing, all other command line

options are saved in the Windows registry under:

small

```
HKEY\_LOCAL\_MACHINE\\SYSTEM\\CurrentControlSet\\Services\\TAOImR
```

These options are used when the service is started. The `install_no_imr` option should be used when installing the Activator on a separate machine with no ImR, otherwise the installation will ensure that the ImR is always started before the Activator by setting a dependency between the two services. Note Only a single Activator can be installed as a Windows service due to the way the start-up options are stored in the registry.

## 9.7.2 Examples

Start the ImR Activator with default options:

```
$ ./tao_imr_activator
```

and, the output are:

```
ImR Activator: Starting MYHOST
... Multicast error message omitted
ImR Activator: Not registered with ImR.
```

Start the ImR Activator with debug level 2, store the Activators stringified IOR in a file, and register with an ImR that was started with multicast discovery enabled:

```
$ ./tao_imr_activator d 2 o activator.ior
```

and, the output are:

```
ImR Activator: Starting MYHOST
ImR Activator: Registered with ImR.
```

Install the ImR Activator as a Windows service on a machine with no ImR:

```
$ tao_imr_activator.exe d 2 o activator.ior c install_no_imr
```



# 10 Interface Repository

Run-time type information in CORBA is managed by the ORB's *Interface Repository* (IR) component. It allows to request, inspect and modify IDL type information dynamically, e.g., to find out which operations an object supports. Some ORBs may also need the IR to find out whether a given object's type is a subtype of another, but most ORBs can do without the IR by encoding this kind of type information in the helper classes generated by the IDL compiler.

In essence, the IR is just another remotely accessible CORBA object that offers operations to retrieve (and in theory also modify) type information.

## 10.1 Type Information in the IR

The IR manages type information in a hierarchical containment structure that corresponds to the structure of scoping constructs in IDL specifications: modules contain definitions of interfaces, structures, constants etc. Interfaces in turn contain definitions of exceptions, operations, attributes and constants. Figure 10.1 illustrates this hierarchy.




Figure 10.1: Containers in the Interface Repository

The descriptions inside the IR can be identified in different ways. Every element of the repository has a unique, qualified name which corresponds to the structure of name scopes in the IDL specification. An

interface `I1` which was declared inside module `M2` which in turn was declared inside module `M1` thus has a qualified name `M1::M2::I1`. The IR also provides another, much more flexible way of naming IDL constructs using *Repository Ids*. There are a number of different formats for *RepositoryIds* but every Repository must be able to handle the following format, which is marked by the prefix "IDL:" and also carries a suffix with a version number, as in, e.g., "IDL:jacorb/demo/grid:1.0". The name component between the colons can be set freely using the IDL compiler directives `#pragma prefix` and `#pragma ID`. If no such directive is used, it corresponds to the qualified name as above.

## 10.2 Repository Design

When designing the Interface Repository, our goal was to exploit the Java reflection API's functionality to avoid having to implement an additional data base for IDL type descriptions. An alternative design is to use the IR as a back-end to the IDL compiler, but we did not want to introduce such a dependency and preferred to have a rather "light-weight" repository server. As it turned out, this design was possible because the similarities between the Java and CORBA object models allow us to derive the required IDL information at run time. As a consequence, we can even do without any IDL at compile time. In addition to this simplification, the main advantage of our approach lies in avoiding redundant data and possible inconsistencies between persistent IDL descriptions and their Java representations, because Java classes have to be generated and stored anyway.

Thus, the Repository has to load Java classes, interpret them using reflection and translate them into the appropriate IDL meta information. To this end, the repository realizes a reverse mapping from Java to IDL. Figure 10.2 illustrates this functionality, where  $f^{-1}$  denotes the reverse mapping, or the inverse of the language mapping.




Figure 10.2: The JacORB Interface Repository

## 10.3 Using the IR

For the ORB to be able to contact the IR, the IR server process must be running. To start it, simply type the `ir` command and provide the required arguments:

```
$ ir /home/brose/classes /home/brose/public_html/IR.Ref
```

The first argument is a path to a directory containing `.class` files and packages. The IR loads these classes and tries to interpret them as IDL compiler-generated classes. If it succeeds, it creates internal representations of the adequate IDL constructs. See below for instructions on generating classes with IR information. The second argument on the command line above is simply the name of the file where the IR stores its object reference for ORB bootstrapping.

To view the contents of the repository, you can use the GUI IRBrowser tool or the query command. First, let's query the IR for a particular repository ID. JacORB provides the command `qir` ("query IR") for this purpose:

```
$ qir IDL:raccoon/test/cyberchair/Paper:1.0
```

As result, the IR returns an `InterfaceDef` object, and `qir` parses this and prints out:

```
interface Paper
{
    void read(out string arg_0);
    raccoon::test::cyberchair::Review getReview(in long arg_0);
    raccoon::test::cyberchair::Review submitReview(
        in string arg_0, in long a rg_1);
    void listReviews(out string arg_0);
};
```

To start the IRBrowser, simply type

```
$ irbrowser [ -i <IOR-string> | -f <filename>]
```

e.g.

```
$ irbrowser
```

Note that if no arguments are supplied it will default to using `resolve_initial_references`.

Figure 10.3 gives a screen shot of the IR browser.

The Java classes generated by the IDL compiler using the standard OMG IDL/Java language mapping do not contain enough information to rebuild all of the information contained in the original IDL file. For example, determining whether an attribute in an interface was `readonly` or not is not possible, or telling the difference between `in` and `inout` parameter passing modes. Moreover, IDL modules are not explicitly represented in Java, so telling whether a directory in the class path represents an IDL module is not easily possible. For these reasons, the JacORB IDL compiler generates a few additional classes that hold the required extra information if the compiler switch `-ir` is used when compiling IDL files:

```
$ idl -ir myIdlFile.idl
```

The additional files generated by the compiler are:

- a `_XModule.java` class file for any IDL module X
- a `YIRHelper.java` class file for any interface Y.

**If no `.class` files that are compiled from these extra classes are found in the class path passed to the IR server process, the IR will not be able to derive any representations.** Note that the IDL compiler does not make any non-compliant modifications to any of the standard files that are defined in the Java language mapping — there is only additional information.

One more caveat about these extra classes: The compiler generates the `_XModule.java` class only for genuine modules. Java package scopes created by applying the `-d` switch to the IDL compiler do not represent proper modules and thus do not generate this class. Thus, the contents of these directories will not be considered by the IR.

When an object's client calls the `get_interface()` operation, the ORB consults the IR and returns an `InterfaceDef` object that describes the object's interface. Using `InterfaceDef` operations on this description object, further description objects can be obtained, such as descriptions for operations or attributes of the interface under consideration.

The IR can also be called like any other CORBA object and provides `lookup()` or `lookup_name()` operations to clients so that definitions can be searched for, given a qualified name. Moreover, the complete contents of individual containers (modules or interfaces) can be listed.

Interface Repository meta objects provide further description operations. For a given `InterfaceDef` object, we can inspect the different meta objects contained in this object (e.g., `OperationDef` objects). It is also possible to obtain descriptions in form of a simple structure of type `InterfaceDescription` or `FullInterfaceDescription`. Since structures are passed by value and a `FullInterfaceDescription` fully provides all contained descriptions, no further — possibly remote — invocations are necessary for searching the structure.

## 10.4 Interaction between `#pragma` prefix and `-i2jpackage`

Generally any use of `#pragma prefix` or `-i2jpackage` should be avoided. If you intend to use a IDL file with the Interface Repository. If there is no other option there is a property that allows you to circumvent that restriction in some cases. Note however that this is a non-standard extension.

If, for example you have the following IDL file:

```
#pragma prefix "org.jacorb.test"

module ir
{
    typedef string StringAlias;
    typedef sequence<StringAlias> StringAliasList;
```

```
struct TestStruct
{
    StringAliasList stringList;
};
};
```

As you want your generated java files to reside in the package `org.jacorb.test.ir` you need to add `-i2jpackage` as an argument to the `idl` command. `$ idl -ir -i2jpackage ir:org.jacorb.test.ir myIdlFile.idl` Now the generated files are in the directory `org/jacorb/test/ir`.

As the IR starts it reads in the generated classes and implicitly creates their Repository ID's solely based on the directory structure. e.g. the struct `TestStruct` will get the Repository ID `IDL:org/jacorb/test/ir/TestStruct:1.0` however the correct Repository ID is `IDL:org.jacorb.test/ir/TestStruct:1.0`.

This will make it impossible for you to lookup the correct Repository ID successfully. starting of the IR will fail if the IR itself needs to look up a Repository ID during start.

As a workaround you can specify the property `jacorb.ir.patch_pragma_prefix=on` to the IR server. this property will cause the IR to change the first component of a requested Repository ID (Repository ID's consists of multiple components delimited with `'/'` so its `org.jacorb.test` in this case). If the first component looks like a pragma prefix (contains multiple `'.'`) the `'.'` will be changed to `'/'`.

So the incoming request for `IDL:org.jacorb.test/ir/TestStruct:1.0` will be changed to a request for `IDL:org/jacorb/test/ir/TestStruct:1.0` so that the IR will be able to resolve that.




Figure 10.3: IRBrowser Screenshot

# 11 Dynamic Management of Any Values

by Jason Courage

The purpose of this chapter is to describe the DynAny specification, which is the specification for the dynamic management of Any values. This chapter only describes the main features of the DynAny specification; for the complete specification consult the appropriate chapter of the CORBA specification available from the OMG.

## 11.1 Overview

DynAny objects are used to dynamically construct and traverse Any values. A DynAny can represent a value of a basic type, such as boolean or long, or a constructed type, such as enum or struct.

## 11.2 Interfaces

The UML diagram below shows the relationship between the interfaces in the org.omg.DynamicAny module.




Figure 11.1: DynAny Relationships

The DynAny interface is the base interface that represents values of the basic types. For each constructed type there is a corresponding interface that extends the DynAny interface and defines operations specific to the constructed type. The table below lists the interfaces in the DynamicAny module and the types they represent.

Interface	Type
DynAny	basic types (boolean, long, etc.)
DynFixed	fixed
DynEnum	enum
DynStruct	struct
DynUnion	union
DynSequence	sequence
DynArray	array
DynValue*	non-boxed valuetype
DynValueBox*	boxed valuetype

\* Not currently implemented by JacORB.

## 11.3 Usage Constraints

Objects that implement interfaces in the DynamicAny module are intended to be local to the process that constructs and uses them. As a result, references to these objects cannot be exported to other processes or externalized using `ORB::object_to_string`; an operation that attempts to do so will throw the MARSHAL system exception.

## 11.4 Creating a DynAny Object

The DynAnyFactory interface is used to create a DynAny object. There are two operations for creating a DynAny object; these are listed in the table below.

Operation	Description
<code>create_dyn_any</code>	Constructs a DynAny object from an Any value
<code>create_dyn_any_from_type_code</code>	Constructs a DynAny object from a TypeCode

The example below illustrates how to obtain a reference to the DynAnyFactory object and then use it to construct a DynAny object with each of the create operations. Exception handling is omitted for brevity.

The following line of code imports the classes in the DynamicAny package.

```
import org.omg.DynamicAny.*;
```



The following code segment obtains a reference to the DynAnyFactory object.

```
DynAnyFactory factory = null;
DynAny DynAny = null;
DynAny DynAny2 = null;
org.omg.CORBA.Any any = null;
org.omg.CORBA.TypeCode tc = null;
org.omg.CORBA.Object obj = null;

// obtain a reference to the DynAnyFactory
obj = orb.resolve_initial_references ("DynAnyFactory");

// narrow the reference to the correct type
factory = DynAnyFactoryHelper.narrow (obj);
```

The following code segment creates a DynAny with each of the create operations.

```
// create a DynAny object from an Any
any = orb.create_any ();
any.insert_long (1);
DynAny = factory.create_dyn_any (any);

// create a DynAny object from a TypeCode
tc = orb.get_primitive_tc (org.omg.CORBA.TCKind.tk_long);
DynAny2 = factory.create_dyn_any_from_type_code (tc);
```

If the Any value or TypeCode represents a constructed type then the DynAny can be narrowed to the appropriate subtype, as illustrated below.

The following IDL defines a struct type.

```
// example struct type
struct StructType
{
    long field1;
    string field2;
};
```

The following code segment illustrates the creation of a DynStruct object that represents a value of type StructType.

```

StructType type = null;
DynStruct dynStruct = null;

// create an Any that contains an object of type StructType
type = new StructType (999, "Hello");
any = orb.create_any ();
StructTypeHelper.insert (any, type);

// construct a DynAny from an Any and narrow it to a DynStruct
dynStruct = (DynStruct) factory.create_dyn_any (any);

```

## 11.5 Accessing the Value of a DynAny Object

The DynAny interface defines a set of operations for accessing the value of a basic type represented by a DynAny object. The operation to get a value of basic type <type> from a DynAny has the form `get_<type>`. The operation to insert a value of basic type <type> into a DynAny has the form `insert_<type>`. A `TypeMismatch` exception is thrown if the type of the operation used to get/insert a value into a DynAny object does not match the type of the DynAny.

The operations for accessing the value of a constructed type represented by a DynAny are defined in the interface specific to the constructed type. For example, the `DynStruct` interface defines the operation `get_members`, which returns a sequence of name/value pairs representing the members of the struct or exception represented by a `DynStruct` object.

## 11.6 Traversing the Value of a DynAny Object

DynAny objects can be viewed as an ordered collection of component DynAnys. For example, in a `DynStruct` object the ordered collection of component DynAnys is the members of the struct or exception it represents. For DynAny objects representing basic types or constructed types that do not have components, the collection of component DynAnys is empty.

All DynAny objects have a current position. For DynAnys representing constructed types that have components, the current position is the index of the component DynAny that would be obtained by a call to the `current_component` operation (described in the table below). The component DynAnys of a DynAny object are indexed from 0 to  $n-1$ , where  $n$  is the number of components. For DynAnys representing basic types, or constructed types that do not have components, the current position is fixed at the value  $-1$ .

The operations for traversing the component DynAnys of a DynAny object are common to all DynAny subtypes, hence they are defined in the DynAny base interface. The table below lists the operations available for traversing a DynAny object.

Operation	Description
-----------	-------------

Operation	Description
seek	Sets the current position to the specified index
rewind	Sets the current position to the first component (index 0)
next	Advances the current position to the next component
component_count	Returns the number of components
current_component	Returns the component at the current position

The following code segment illustrates one way of traversing the component DynAnys of a DynStruct object. As the DynStruct is traversed, the value of each component is obtained and printed. Exception handling is omitted for brevity.

```
DynAny curComp = null;

// print the value of the first component
curComp = dynStruct.current_component ();
System.out.println ("field1 = " + curComp.get_long ());

// advance to the next component
dynStruct.next ();

// print the value of the second component
curComp = dynStruct.current_component ();
System.out.println ("field2 = " + curComp.get_string ());
```

The next code segment illustrates another way to perform the same task.

```
// go back to the first component
dynStruct.rewind (); // same as calling seek (0)

// print the value of the first component
System.out.println ("field1 = " + dynStruct.get_long ());

// advance to the next component
dynStruct.seek (1);

// print the value of the second component
System.out.println ("field2 = " + dynStruct.get_string ());
```

As the second code segment illustrates, if the component `DynAny` represents a basic type, its value can be extracted (or inserted) by calling the accessor operation on the parent `DynAny` directly, rather than first obtaining the component using the `current_component` operation.

## 11.7 Constructed Types

This section describes the interfaces in the `DynamicAny` module that represent the constructed types supported by JacORB. Each of these interfaces extends the `DynAny` interface.

### 11.7.1 DynFixed

A `DynFixed` object represents a fixed value. Since IDL does not have a generic type to represent a fixed type, the operations in this interface use the IDL string type. The value represented by a `DynFixed` object can be accessed (as a string) using the `get_value` and `set_value` operations.

A `DynFixed` object has no components.

### 11.7.2 DynEnum

A `DynEnum` object represents a single enumerated value. The integer (ordinal) value of the enumerated value can be accessed with the `get_as_ulong` and `set_as_ulong` operations. The string (IDL identifier) value of the enumerated value can be accessed with the `get_as_string` and `set_as_string` operations.

A `DynEnum` object has no components.

### 11.7.3 DynStruct

A `DynStruct` object represents a struct value or an exception value. The `current_member_name` and `current_member_kind` operations return the name and `TCKind` value of the `TypeCode` of the member at the current position of the `DynStruct`. The members of the `DynStruct` can be accessed with the `get_members` and `set_members` operations.

The component `DynAnys` of a `DynStruct` object are the members of the struct or exception. A `DynStruct` representing an empty exception has no components.

### 11.7.4 DynUnion

A `DynUnion` object represents a union value. The value of the discriminator can be accessed using the `get_discriminator` and `set_discriminator` operations.

If the discriminator is set to a value that names a member of the union then that member becomes active. Otherwise, if the value of the discriminator does not name a member of the union then there is no active member.

If there is an active member, the member operation returns its value as a DynAny object, and the member\_name and member\_kind operations return its name and the TCKind value of its TypeCode. These operations throw an InvalidValue exception if the union has no active member.

A DynUnion object can have either one or two components. The first component is always the discriminator value. The second component is the value of the active member, if one exists.

### 11.7.5 DynSequence

A DynSequence object represents a sequence. The length of the sequence can be accessed using the get\_length and set\_length operations. The elements of the sequence can be accessed using the get\_elements and set\_elements operations.

The component DynAnys of a DynSequence object are the elements of the sequence.

### 11.7.6 DynArray

A DynArray object represents an array. The elements of the array can be accessed using the get\_elements and set\_elements operations.

The component DynAnys of a DynArray object are the elements of the array.

## 11.8 Converting between Any and DynAny Objects

The DynAny interface defines operations for converting between Any objects and DynAny objects. The from\_any operation initialises the value of a DynAny with the value of a specified Any. A TypeMismatch exception is thrown if the type of the Any does not match the type of the DynAny. The to\_any operation creates an Any from a DynAny.

As an example of how these operations might be useful, suppose one wants to dynamically modify the contents of some constructed type, such as a struct, which is represented as an Any. The following steps will accomplish this task:

1. A DynStruct object is constructed from the TypeCode of the struct using the DynAnyFactory::create\_dyn\_any\_from\_type\_code operation.
2. The DynAny::from\_any operation is used to initialise the value of the DynStruct with the value of the Any.
3. The contents of the DynStruct can now be traversed and modified.
4. A new Any can be created to represent the modified struct using the DynAny::to\_any operation.

## 11.9 Further Examples

The demo/dynany directory of the JacORB repository contains example code illustrating the use of DynAny objects. Further code can be found in the org.jacorb.test.orb.dynany package of the JacORB-Test repository.

# 12 Objects By Value

Until CORBA 2.3, objects could only be passed using reference semantics: there was no way to specify that object state should be copied along with an object reference. A further restriction of the earlier CORBA versions was that all non-object types (structs, unions, sequences, etc.) were values, so you could not use, e.g. a reference-to-struct to construct a graph of structure values that contained shared nodes. Finally, there was no inheritance between structs.

All these shortcomings are addressed by the objects-by-value (OBV) chapters of the CORBA specification: the addition of stateful value types supports copy semantics for objects and inheritance for structs, boxed value types introduce reference semantics for base types, and abstract interfaces determine whether an argument is sent by-value or by-reference by the argument's runtime type. The introduction of OBV into CORBA presented a major shift in the CORBA philosophy, which had been to strictly avoid any dependence on implementation details (state, in particular). It also added a considerable amount of marshaling complexity and interoperability problems. (As a personal note: Even in CORBA 2.6, the OBV marshaling sections are still not particularly precise...)

JacORB 2.0 implements most of the OBV specification. Boxed value types and regular value types work as prescribed in the standard (including value type inheritance, recursive value types, and factories). Still missing in the current implementation is run-time support for abstract value types (although the compiler does accept the corresponding IDL syntax), and the marshaling of truncatable value types does not yet meet all the standard's requirements (and should thus be called "beta").

## 12.1 Example

To illustrate the use of various kinds of value types, here's an example which is also part of the demo programs in the JacORB distribution. The demo shows the use of boxed value types and a recursive stateful value type. Here's the IDL definition from `demo/value/server.idl`:

```
module demo {
  module value {

    valuetype boxedLong    long;
    valuetype boxedString  string;

    valuetype Node {
      public long id;
      public Node next;
    };
  };
};
```

```

interface ValueServer {
    string receive_long    (in boxedLong p1, in boxedLong p2);
    string receive_string (in boxedString s1, in boxedString s2);
    string receive_list    (in Node node);
};
};
};

```

From the definition of the boxed value type `boxedLong` and `boxedString`, the IDL generates the following Java class, which is simply a holder for the long value. No mapped class is generated for the boxed string value type.

```

package demo.value;

public class boxedLong
    implements org.omg.CORBA.portable.ValueBase
{
    public int value;
    private static String[] _ids = { boxedLongHelper.id() };

    public boxedLong(int initial )
    {
        value = initial;
    }
    public String[] _truncatable_ids()
    {
        return _ids;
    }
}

```

The boxed value definitions in IDL above permit uses of non-object types that are not possible with IDL primitive types. In particular, it is possible to pass Java `null` references where a value of a boxed value type is expected. For example, we can call the operation `receive_long` and pass one initialized `boxedLong` value and a null reference, as show in the following snippet from the client code:

```

ValueServer s = ValueServerHelper.narrow( obj );
boxedLong boxL = new boxedLong (774);

System.out.println ("Passing two integers: "
                    + s.receive_long ( boxL , null ));

```

With a regular `long` parameter, a `null` reference would have resulted in a `BAD_PARAM` exception. With boxed value types, this usage is entirely legal and the result string returned from the `ValueServer` object is `''one or two null values''`.



A second new possibility of the reference semantics that can be achieved by “boxing” primitive IDL types is sharing of values. With primitive values, two variables can have copies of the same value, but they cannot both refer to the same value. This means that when one of the variables is changed, the other one retains its original value. With shared values that are referenced, both variables would always point to the same value.

The stateful value type `Node` is implemented by the programmer in a class `NodeImpl` (see the JacORB distribution for the actual code). The relationship between this implementation class and the corresponding IDL definition is not entirely trivial, and we will discuss it in detail below.

## 12.2 Factories

When an instance of a (regular) value type is marshaled over the wire and arrives at a server, a class that implements this value type must be found, so that a Java object can be created to hold the state information. For interface types, which are only passed by reference, something similar is accomplished by the POA, which accepts remote calls to the interface and delivers them to a local implementation class (the servant). For value type instances, there is no such thing as a POA, because they cannot be called remotely. Thus, the ORB needs a different mechanism to know which Java implementation class corresponds to a given IDL value type.

The CORBA standard introduces value factories to achieve this. Getting your value factories right can be anywhere from trivial to tricky (we will cover the details in a minute), and so the standard suggests that ORBs also provide convenience mechanisms to relieve programmers from writing value factories if possible. JacORB’s convenience mechanism is straightforward:

If the implementation class for an IDL value type A is named AImpl, resides in the same package as A, and has a no-argument constructor, then no value factory is needed for that type.

In other words, if your implementation class follows the common naming convention (“...Impl”), and it provides a no-arg constructor so that the ORB can instantiate it, then the ORB has all that it needs to (a) find the implementation class, and (b) create an instance of it (which is then initialized with the unmarshaled state from the wire).

This mechanism ought to save you from having to write a value factory 99% of the time. It works for all kinds of regular value types, including those with inheritance, and recursive types (where a type has members of its own type).

If you do need more control over the instance creation process, or the unmarshaling from the wire, you can write your own value factory class and register it with the ORB using `ORB.register_value_factory(repository_id, factory)`. The factory object needs to implement the interface `org.omg.CORBA.portable.ValueFactory`, which requires a single method:

```
public Serializable read_value (InputStream is);
```

When an instance of type repository\_id arrives over the wire, the ORB calls the `read_value()`

method, which must unmarshal the data from the input stream, create an instance of the appropriate implementation class from it, and return that.

The easiest way to implement this method is to create an instance of the implementation class, and pass it to the `read_value()` method of the given `InputStream`:

```
public Serializable read_value (InputStream is) {
    A result = new AImpl();
    return is.read_value(result);
}
```

The `InputStream.read_value()` method registers the newly created instance in the stream's indirection table, and then reads the data from the stream and initializes the given `value` instance from it.

The value factory must be registered with the ORB using `register_value_factory()`. As a special convenience (defined in the CORBA standard), if the value factory class for type `A` is called `ADefaultFactory`, then the ORB will find it automatically and use it, unless a different factory has been explicitly registered.

It sometimes causes confusion that you can also define factory methods in a value type's IDL. These factory methods are completely unrelated to the unmarshaling mechanism discussed above; they are simply a portable means to declare what kinds of "constructors" a value type implementation should have. They are purely for local use, but since they are "factories", the corresponding methods must also be implemented in the type's `ValueFactory` implementation.

# 13 IIOP over SSL

Using SSL to authenticate clients and to protect the communication between client and target requires no changes in your source code. The only notable effect is that SSL/TLS type sockets are used for transport connections instead of plain TCP sockets — and that connection setup takes a bit longer.

The only prerequisites are that set up a key store file that holds your cryptographic keys, and to configure SSL by setting a few properties. All of this is described in this chapter.

## 13.1 Key stores

SSL relies on public key certificates in the standard X.509 format. These certificates are presented in the authentication phase of the SSL handshake and used to compute and exchange session keys.

The Java 2 security API provides interfaces that access a persistent data structure called KeyStore. A key store is simply a file that contains public key certificates and the corresponding private keys. It also contains other certificates that can be used to verify public key certificates. All cryptographic data is protected using passwords and accessed using names called aliases.

The following section explain how to create key stores for Sun JSSE.

### 13.1.1 Setting up a JSSE key store

To set up key stores with JSSE you can use Java's `keytool`. In order to generate a simple public key infrastructure you can perform the following steps:

1. Create a new key store containing a new public/private key pair with `keytool`. The public key will be wrapped into a self-signed certificate.
2. Export the self-signed certificate from the key store into a file.
3. Import the self-signed certificate into a trust store (or configure that trustees shall be read from key store, see below).

To create a new key store containing a new public/private key pair type:

```
keytool -genkey -alias <alias> -keystore <keystore>
```

If you don't give a key store name `keytool` will create a key store with the name `.keystore` in the user's home directory. The command given above will ask for the following input:

```
Enter keystore password:  changeit
What is your first and last name?
  [Unknown]:  Developer
What is the name of your organizational unit?
  [Unknown]:  cs
What is the name of your organization?
  [Unknown]:  PrismTech
What is the name of your City or Locality?
  [Unknown]:  Berlin
What is the name of your State or Province?
  [Unknown]:  Berlin
What is the two-letter country code for this unit?
  [Unknown]:  Germany
Is CN=Developer, OU=cs, O=PrismTech, L=Berlin, ST=Berlin,
  C=Germany correct?
  [no]:  yes

Enter key password for <testkey>
  (RETURN if same as keystore password):  testkey
```

You can view the entries of the newly created keystore by typing:

```
keytool -keystore <keystore> -list -storepass <password>
```

The output will read for example like this:

```
Keystore type: jks
Keystore provider: SUN

Your keystore contains 1 entry

testkey, Dec 1, 2004, keyEntry,
Certificate fingerprint (MD5): C4:9B:11:97:FF:CD:4C:C9:B3:02:BB:
9A:46:D8:C3:11
```

Now you have a public key certificate that you can present for authentication. The public key contained in the key store is wrapped into a self-signed certificate. This self-signed certificate has to be added to the Java trust store. To do this export the certificate from the key store and import it into the Java trust store located in `<java_home>/jre/lib/security/cacerts`.

To export the self-signed certificate into a file type:

```
keytool -export -keystore <keystore> -alias <alias> -file <filename>
```

To import the certificate into the trust store type:

```
keytool -import -keystore <truststore> -alias <alias> -file <filename>
```

More documentation on key stores can be found in the Java tool documentation for the `keytool` command. Note that if you care for “real” security, be advised that setting up and managing (or finding) a properly administered CA is essential for the overall security of your system.

### 13.1.2 Step–By–Step certificate creation

In order to generate a simple public key infrastructure you can perform the following steps:

1. Create new key stores (File/new) and keypairs (Keys/new) for the CA and for the user.
2. Open the user key store (File/open), select the key entry and export the self-signed certificate (Certificates/Export).
3. Open the CA key store and add the user certificate as a Trustee (Trustees/add...).
4. Select the trusted user certificate and create a signed public key certificate (Certificates/Create). Leave the role name field empty, enter the CAs private key password and save the new certificate by clicking OK.
5. Export the CAs self-signed certificate to a file (as explained above). Delete the trusted certificate from the CA key store (Trustees/Delete).
6. Open the user key store again. Select the key entry, the import the CA-signed user cert (Certificates/Import), and the self-signed CA cert.
7. Add the self-signed CA cert as a trustee. This is only needed for verifying the chain, therefore the key store can be deployed without it. Please note that a failed verification might result in a `SignatureException`.

## 13.2 Configuring SSL properties

When the ORB is initialized by the application, a couple of properties are read from files and the command line. To turn on SSL support, you have to set the following property to “on”:

```
jacorb.security.support_ssl=on
```

This will just load the SSL classes on startup. The configuration of the various aspects of SSL is done via additional properties.

Configure which SSL socket factory and SSL server socket factory shall be used with the properties:

```
jacorb.ssl.socket_factory=qualified classname  
jacorb.ssl.server_socket_factory=qualified classname
```

If you want to use JSSE, then configure the following as qualified classname of SSL Socket Factory and SSL server socket factory:

```
org.jacorb.security.ssl.sun_jsse.SSLSocketFactory
org.jacorb.security.ssl.sun_jsse.SSLServerSocketFactory
```

As explained in the previous section, cryptographic data (key pairs and certificates) is stored in a key store file. To configure the file name of the key store file, you need to define the following property:

```
jacorb.security.keystore=AKeystoreFileName
```

The key store file name can either be an absolute path or relative to the home directory. Key stores are searched in this order, and the first one found is taken. If this property is not set, the user will be prompted to enter a key store location on ORB startup.

The password for the key store file can be specified by using the property `jacorb.security.keystore_password`.

```
jacorb.security.keystore_password=secret
```

By default the `KeyStore` type uses `JKS`; to change this alter the property `jacorb.security.keystore_type`.

The SSL socket factory algorithms are initialised by default to `SunX509`. On other JDK implementations (e.g. IBM) this can be changed (to e.g. `IbmX509`) by altering the following properties:

```
jacorb.security.jsse.server.key_manager_algorithm=SunX509
jacorb.security.jsse.server.trust_manager_algorithm=SunX509
jacorb.security.jsse.client.key_manager_algorithm=SunX509
jacorb.security.jsse.client.trust_manager_algorithm=SunX509
```

To avoid typing in lots of aliases and passwords (one for the key store, and one for each entry that is used), you can define default aliases and passwords like this:

```
# the name of the default key alias to look up in the key store
jacorb.security.default_user=brose
jacorb.security.default_password=jacorb
```

Note that when using Sun JSSE: The `javax.net.ssl.trustStore[Password]` properties doesn't seem to take effect, so you may want to add trusted certificates to "normal" key stores. In this case configure JacORB to read certificates from the key store rather than from a dedicated trust store, please set the property

```
jacorb.security.jsse.trustees_from_ks=on
```

SSL settings can be further refined using security options as in the following property definitions:

```
jacorb.security.ssl.client.supported_options=0
jacorb.security.ssl.client.required_options=0

jacorb.security.ssl.server.supported_options=0
jacorb.security.ssl.server.required_options=0
```

The value of these security options is a bit mask coded as a hexadecimal integer. The meanings of the individual bits is defined in the CORBA Security Service Specification and reproduced here from the `Security.idl` file:

```
typedef unsigned short    AssociationOptions;

const AssociationOptions NoProtection = 1;
const AssociationOptions Integrity = 2;
const AssociationOptions Confidentiality = 4;
const AssociationOptions DetectReplay = 8;
const AssociationOptions DetectMisordering = 16;
const AssociationOptions EstablishTrustInTarget = 32;
const AssociationOptions EstablishTrustInClient = 64;
const AssociationOptions NoDelegation = 128;
const AssociationOptions SimpleDelegation = 256;
const AssociationOptions CompositeDelegation = 512;
```

### 13.2.1 Protocols

The JSSE is capable of supporting SSL versions 2.0 and 3.0 and Transport Layer Security (TLS) 1.0. To enable different protocols in the JSSE layer use the below properties.

```
jacorb.security.ssl.client.protocols
jacorb.security.ssl.server.protocols
```

Refer to the JSSE documentation for valid `SSLContext`/`SSLContext` protocol values.

### 13.2.2 Client side and server side configuration

On both the client side and the server side supported and required options can be configured. The following tables explain the settings for supported and required options for client and server.

Table 13.1: Client side supported options

Property with value	Description
jacorb.security.ssl. client.supported_options=20 // EstablishTrustInTarget	This value indicates that the client can use SSL. Actually, this is default SSL behaviour and must always be supported by the client.
jacorb.security.ssl. client.supported_options=40 // EstablishTrustInClient	This makes the client load it's own key/certificate from it's key store, to enable it to authenticate to the server.

Table 13.2: Client side required options

Property with value	Description
jacorb.security.ssl. client.required_options=20 // EstablishTrustInTarget	This enforces SSL to be used.
jacorb.security.ssl. client.required_options=40 // EstablishTrustInClient	This enforces SSL to be used. Actually, this is no meaningful value, since in SSL, the client can't force it's own authentication to the server.

Table 13.3: Server side supported options

Property with value	Description
jacorb.security.ssl. server.supported_options=1 // NoProtection	This tells the clients that the server also supports unprotected connections. If NoProtection is set, no required options should be set as well, because they override this value.
jacorb.security.ssl. server.supported_options=20 // EstablishTrustInTarget	This value indicates that the server supports SSL. Actually, this is default SSL behaviour and must always be supported by the server. This also makes the server load it's key/certificate from the key store.
jacorb.security.ssl. server.supported_options=40 // EstablishTrustInClient	This value is ignored, because authenticating the client is either required, or not done at all (the client can't force its own authentication).



Table 13.4: Server side required options

<b>Property with value</b>	<b>Description</b>
jacorb.security.ssl. server.required_options=20 // EstablishTrustInTarget	This enforces SSL to be used.
jacorb.security.ssl. server.required_options=40 // EstablishTrustInClient	This enforces SSL to be used, and will request the client to authenticate. It also will load trusted certificates for the authentication process.

## 13.3 SecureRandom Plugin System

Under certain platforms (e.g. J2ME CDC platforms) when the JSSE initializes its random number generator it may spawn a large number of threads and/or have a significant start-up time. This overhead may be unacceptable.

In order to allow developers to provide their own initialization routines for SecureRandom a plugin class may be provided. A developer should implement the following interface.

```
package org.jacorb.security.ssl.sun_jsse;

public interface JSRandom
{
    SecureRandom getSecureRandom ();
}
```

The classname should then be specified in the property

```
jacorb.security.randomClassPlugin
```

which will be instantiated at runtime. If this property has been specified the SSLSocket factories will call getSecureRandom to pass through to the SSLContext. Otherwise, the JSSE will use its default values.

Two example implementations; JSRandomImpl and JSRandomImplThread are provided. JSRandomImpl explicitly initializes a SecureRandom with a fixed seed value. Note that the seed is a hardcoded value (4711). As using such a seed is a security risk it is not recommended that this code be used in a production system. The second, using initSecureRandom (see below)

```
public class JSRandomImplThread implements JSRandom {

    public static void initSecureRandom() { ... }

}
```

allows the developer to initialize a single static SecureRandom in a separate thread at the start of their main before any ORB calls are done.

## 13.4 Security and corbaloc

If you want to put together a corbaloc that points to your SSL enabled server object the following needs to be ensured:

normally an IOR string contains additional components that describe the exact SSL setup for a given server object. However this additional information cannot be attached to a corbaloc. JacORB provides an extensions to address that shortcoming.

By using the JacORB specific protocol extension `ssliop` you can tell ORB that the corbaloc points to a SSL enabled target. When the corbaloc is resolved with `orb.string_to_object()` and the protocol extension is set, JacORB will act as the target had the SSL specific tagged components set<sup>1</sup>.

By default the SSL option `EstablishTrustInTarget` will be used both for supported and required SSL options of the created stub. Using the property `jacorb.security.ssl.corbaloc_ssliop.supported_options` this can be further customized. Have a look at the configuration chapter for more details.

Example of a corbaloc

```
corbaloc:ssliop:1.2@hostname:port/object_key
```

---

<sup>1</sup>you need to ensure that the corbaloc used GIOP v1.2 as otherwise tagged components are not supported



# 14 MIOP

JacORB has an implementation of MIOP written as an ETF plugin. This conforms to version 01-11-08 of the Unreliable Multicast Inter-ORB Protocol specification. Note that subsections 29.12 (MIOP Gateway) and 29.13 (Multicast Group Manager) are not implemented.

## 14.1 Enabling the MIOP Transport

In order to enable the ETF transport plugin the following configuration properties must be altered.

```
jacorb.transport.factories
jacorb.transport.client.selector
```

By default these properties are configured to use the IIOP transport. For example to select both IIOP and MIOP transports:

```
jacorb.transport.factories=org.jacorb.orb.iiop.IIOPFactories,
                           org.jacorb.orb.miop.MIOPFactories
jacorb.transport.client.selector=
                           org.jacorb.orb.miop.MIOPProfileSelector
```

## 14.2 Configuring the MIOP Transport

A number of extra configuration properties have been added for the transport.

Table 14.1: MIOP Configuration

Property	Description	Type
jacorb.miop.timeout	Timeout used in MIOP requests. Default is 100.	integer
jacorb.miop.time_to_live	TTL used for multicast UDP packets. Default is 5 seconds.	integer
jacorb.miop.incomplete_messages_threshold	Maximum number of incomplete messages allowed. Default 5.	integer
jacorb.miop.message_completion_timeout	Timeout for packet collection to be completed. Default 500ms.	integer

Table 14.1: MIOP Configuration

Property	Description	Type
jacorb.miop.packet_max_size	This is the maximum size of the frame buffer. This defaults to 1500 bytes which is the typical value for most network interfaces. From this the IP, UDP and UMIOP headers will be deducted which will leave 1412 bytes for the MIOP packet.	integer

## 14.3 MIOP Example

A new demo has been included within <JacORB>/demo/miop. This section will describe how to run this demo including its use of MIOP corbaloc strings.

Assuming the developer has installed Ant version 1.7.1 or above then the example may be compiled by typing `ant` within the <JacORB>/demo/miop directory. The classes will be compiled to <JacORB>/classes which may need to be added to the classpath.

To run the server:

```
jaco demo.miop.Server
```

To run the client:

```
jaco demo.miop.Client
```

This is the simplest configuration and will simply send two oneway requests via UDP to the server. By default the Server will write out a `miop.ior` file containing the following corbaloc:

```
corbaloc:miop:1.0@1.0-TestDomain-1/224.1.239.2:1234;
    iiop:1.2@10.1.1.0.4:38148/4222541922/%00%16%0F%205=%25%02%01I%0C
```

The Group IIOP Profile key string will not remain constant. The server takes a single optional argument:

```
-noGroupProfile      Don't write IIOP Group Profile request.
```

This will create a corbaloc as shown below and is useful for interoperating with ORBs that do not support the Group Profile.

```
corbaloc:miop:1.0@1.0-TestDomain-1/224.1.239.2:1234
```

The Client takes two optional arguments:

-fragment	Trigger fragmentation by sending a larger request.
[IOR—Corbaloc]	Don't use miop.ior but this supplied IOR or Corbaloc.

The second optional argument is useful if interoperating with another ORB.

### 14.3.1 Two way requests and MIOP

The demo client does an `unchecked_narrow` on the supplied `corbaloc/URL`. This is because a MIOP URL does not normally support a two-way `is_a` request unless a Group IIOP profile has also been encoded into the `corbaloc`. By default the JacORB demo server will create the Group IIOP profile as well:

```
corbaloc:miop:1.0@1.0-TestDomain-1/224.1.1.239.2:1234;  
  iiop:1.0@10.1.1.0.4:36840/7150661784/%00%16%0F%1B*@2%02,%1A
```

It is not guaranteed that other ORBs (e.g. TAO) will create the Group IIOP profile.





# 15 BiDirectional GIOP

BiDirectional GIOP has its main use in configurations involving callbacks with applets or firewalls where it sometimes isn't possible to open a direct connection to the desired target. As a small example, imagine that you want to monitor the activities of a server via an applet. This would normally be done via a callback object that the applet registers at the server, so the applet doesn't have to poll the server for events. To accomplish this without BiDirectional GIOP, the server would have to open a new connection to the client which will not work because applets usually are not allowed to act as servers, i.e. open ServerSockets. At this point BiDirectional GIOP can help because it allows to reuse the connection the applet opened to the server for GIOP requests from the server to the applet (which isn't allowed in "standard" GIOP).

## 15.1 Setting up Bidirectional GIOP

Setting up BiDirectional GIOP consists of two steps:

1. Setting an ORBInitializer property and creating the BiDir policy
2. Adding this policy to the servant's POA.

### 15.1.1 Setting the ORBInitializer property

The first thing that is necessary for BiDirectional GIOP to be available is the presence of the following property, which can be added by the usual ways (see chapter 3):

```
org.omg.PortableInterceptor.ORBInitializerClass.bidir_init=  
org.jacorb.orb.giop.BiDirConnectionInitializer
```

If this property is present on ORB startup, the corresponding policy factory and interceptors will be loaded.

### 15.1.2 Creating the BiDir Policy

Creating the necessary BiDir Policy is done via a policy factory hidden in the ORB.

```
import org.omg.BiDirPolicy.*;  
import org.omg.CORBA.*;
```

```
[...]

Any any = orb.create_any();
BidirectionalPolicyValueHelper.insert( any, BOTH.value );

Policy p = orb.create_policy( BIDIRECTIONAL_POLICY_TYPE.value,
                             any );
```

The value of the new policy is passed to the factory inside of an any. The ORB is told to create a policy of the specified type with the specified value. The newly created policy is then used to create a user POA. Please note that if any POA of has this policy set, all connections will be enabled for BiDirectional GIOP, that is even those targeted at object of POAs that don't have this policy set. For the full source code, please have a look at the bidir demo in the demo directory.

## 15.2 Verifying that BiDirectional GIOP is used

From inside of your application, it is impossible to tell whether requests arrived over a unidirectional or BiDirectional connection. Therefore, to check if connections are used in both directions, you can either use a network monitoring tool or take a look at JacORBs output to tell you if your server created a new connection to the client, or if the existing one is being reused.

If the debug level is set to 2 or larger, the following output on the server side will tell you that a connection is being reused:

```
[ ConnectionManager: found conn to target <my IP>:<my port> ]
```

If, on the other hand, the connection is not being reused, the client will show the following output:

```
[ Opened new server-side TCP/IP transport to <my host>:<my port> ]
```

## 15.3 TAO interoperability

There is one problem that may prevent TAO and JacORB to interoperate using BiDirectional GIOP: If JacORB uses IP addresses as host names (JacORBs default) and TAO uses DNS names as host names (TAOs default on non Microsoft Windows platforms), connections from JacORB clients to TAO servers will not be reused. If, on the other hand, both use the same “format” for host addresses, interoperability will be successful. There are two ways to solve this problem:

1. Use `--ORBdotteddecimaladdresses 1` as an command line argument to the TAO server.
2. Configure JacORB to use DNS names (See the configuration guide).

# 16 Portable Interceptors

Since revision 1.1 JacORB provides support for Portable Interceptors. These interceptors are compliant to the standard CORBA specification. Therefore we don't provide any documentation on how to program interceptors but supply a few (hopefully helpful) hints and tips on JacORB specific solutions.

The first step to have an interceptor integrated into the ORB is to register an ORBInitializer. This is done by setting a property the following way:

```
org.omg.PortableInterceptor.ORBInitializerClass.<any_suffix>=  
  <orb initializer classname>
```

For compatibility reasons with the spec, the properties format may also be like this:

```
org.omg.PortableInterceptor.ORBInitializerClass.<orb initializer classname>
```

The suffix is just to distinguish between different initializers and doesn't have to have any meaningful value. The value of the property however has to be the fully qualified classname of the initializer. If the verbosity is set to  $\geq 2$  JacORB will display a `ClassNotFoundException` in case the initializers class is not in the class path.

An example line might look like:

```
org.omg.PortableInterceptor.ORBInitializerClass.my_init=  
  test.MyInterceptorInitializer
```

Unfortunately the interfaces of the specification don't provide any access to the ORB. If you need access to the ORB from out of the initializer you can cast the `ORBInitInfo` object to `jacorb.orb.portableInterceptor.ORBInitInfoImpl` and call `getORB()` to get a reference to the ORB that instantiated the initializer.

When working with service contexts please make sure that you don't use `0x4A414301` as an id because a service context with that id is used internally. Otherwise you will end up with either your data not transferred or unexpected internal exceptions.

## 16.1 Interceptor ForwardRequest Exceptions

Several of the interceptor types may throw a `ForwardException` such as `ClientRequestInterceptor.send_request`. A developer may wish to do this if, for instance, a new policy is being applied to the object to switch to a SSL connection type as suggested within chapter 20.

A current limitation of the specification (CORBA 3; 02-06-33) is that it is impossible to detect whether the call has previously been thrown for the same client request. Thus it is possible to enter an infinite loop throwing `ForwardRequest` at this point. This issue was first submitted to the OMG in May 2002 under number 5266.

In order to allow developers more flexibility when writing their interceptors PrismTech have enhanced the exception handling as follows. We have chosen one of the solutions proposed within issue 5266; namely to allow `forward_reference()` to be accessed in `send_request()` as well as in `receive_other()`. i.e. returning the object from the previous `ForwardRequest` if that has been thrown and null otherwise.

A typical use of this might be

```
public void send_request( ClientRequestInfo ri )
{
    if (ri.effective_profile().tag == TAG_INTERNET_IOP.value &&
        ri.forward_reference() == null)
    {
        // Do some processing, throw a forward request.
    }
}
```

This allows the developer to conditionally throw a forward request while using `forward_reference()` to prevent infinite loops.

## 16.2 Public API

Some users may find it useful to access internal data on the `ClientRequestInfo` and `ServerRequestInfo`. The following API is available. Note that it may be possible to corrupt the call chain so use these at your own risk.

`isLocalInterceptors` returns true if the interceptors are running locally (i.e. no TCP connection is being used and therefore `getConnection` will return null).

### **org.jacorb.orb.portableInterceptor.ServerRequestInfoImpl**

```
public boolean isLocalInterceptors()
public GIOPConnection getConnection()
public ReplyOutputStream getReplyStream ()
public RequestInputStream getRequestStream ()
public ORB orb()
```

### **org.jacorb.orb.portableInterceptor.ClientRequestInfoImpl**

```
public boolean isLocalInterceptors()
```

---

```
public ClientConnection getConnection()  
public ReplyInputStream getReplyStream ()  
public RequestOutputStream getRequestStream ()  
public Delegate getDelegate ()  
public ORB orb()
```



# 17 Asynchronous Method Invocation

JacORB allows you to invoke objects asynchronously, as defined in the [Messaging](#) chapter of the CORBA specification (chapter 22 in CORBA 3.0). Only the callback model is implemented at this time; there is no support for polling yet.

Asynchronous Method Invocation (AMI) means that when you invoke a method on an object, control returns to the caller immediately; it does not block until the reply has been received from the remote object. The results of the invocation are delivered later, as soon as they are received by the client ORB. Asynchronous Invocation is entirely a client-side feature. The server is never aware whether it is invoked synchronously or asynchronously.

In the callback model, replies are delivered to a special [ReplyHandler](#) object that is registered at the client side when the asynchronous invocation is started. Here is a brief example for this (see the [Messaging](#) specification for further details). Suppose you have a Server object, defined in a file server.idl.

```
interface Server
{
    long operation (in long p1, inout long p2);
};
```

The first step is to compile this IDL definition with the “ami\_callback” compiler switch:

```
idl -ami_callback server.idl
```

This lets the compiler generate an additional ReplyHandler class, named AMI.ServerHandler. For each operation of the Server interface, this class has an operation with the same name that receives the return value and out parameters of the original operation. There is an additional method named operation\_except that is called if the invocation raises an exception. If it were defined in IDL, the ReplyHandler class for the above Server would look like this:

```
interface AMI_ServerHandler : Messaging::ReplyHandler
{
    void operation (in long ami_return_val, in long p2);
    void operation_except (in Messaging::ExceptionHolder excep_holder);
};
```

To implement this interface, extend the corresponding POA class (or use the tie approach), as with any CORBA object:

```

public class AMI_ServerHandlerImpl extends AMI_ServerHandlerPOA
{
    public void operation (int ami_return_val, int p2)
    {
        System.out.println ("operation reply received");
    }

    public void operation_excep
        (org.omg.Messaging.ExceptionHolder excep_holder)
    {
        System.out.println ("received an exception");
    }

}

```

For each method *m* of the original Server interface, the IDL compiler generates a special method `sendc_m` into the stub class if the “ami\_callback” switch is on. The parameters of this method are (1) a reference to a ReplyHandler object, and (2) all in or inout parameters of the original operation, with their mode changed to in (out parameters are omitted from this operation). The `sendc` operation does not have a return value.

To actually make an asynchronous invocation, an instance of the ReplyHandler needs to be created, registered with the ORB, and passed to the `sendc` method. The code for this might look as follows:

```

ORB    orb = ...
Server s    = ...

// create handler and obtain a CORBA reference to it
AMI_ServerHandler h = new AMI_ServerHandlerImpl()._this (orb);

// invoke sendc
((_ServerStub)s).sendc_operation (h, 4, 5);

```

Note that the `sendc` operation is only defined in the stub, and therefore the cast is necessary to invoke it. There is not yet any consensus in the OMG whether the `sendc` operation should also be declared in any of the Java interfaces that make up the Server type. Thus, the fact that you need to make a cast to the stub class may change in a future version of JacORB.

If you want to try asynchronous invocations with code such as above, make sure that your client process does something else or at least waits after the invocation has been made, otherwise it will likely exit before the reply can be delivered to the handler.

The Messaging specification also defines a number of CORBA policies that allow you to control the timing of asynchronous invocations. Since these policies are applicable to both synchronous and asynchronous invocations, we describe them in a separate section (see chapter 18).



# 18 Quality of Service

JacORB implements a subset of the QoS policies defined in chapter 22.2 of the CORBA 3.0 specification. In the following, we describe each of the policies we have currently implemented, along with notes on particular JacORB issues concerning each policy. Policies not listed in the following are not yet implemented.

As of yet, all policies described in this chapter are client-side override policies. The CORBA specification uses the term for any policy that is explicitly set and thus overrides system defaults. Policies can be set at different scopes: per object, per thread, or per ORB. The current JacORB implementation only supports object and ORB scopes. In general, the following steps are necessary:

**Step 1.** Get an `any` from the ORB and put the value for the policy into it.

**Step 2.** Get a Policy object from the ORB which encapsulates the desired value (the `any` value from the previous step).

**Step 3.** Apply the policy to a particular object using the `_set_policy_override()` operation on the object reference.

**Step 3.** alternatively: set the policy ORB-wide using the `set_policy_overrides()` operation on the ORB's `PolicyManager` object.

Below is the code that corresponds to the steps listed above, using the `SyncScopePolicy` (described in the following section) as an example. Also, have a look at the demo program in `demo/policies`:

```
SomeCorbaType    server = ...
org.omg.CORBA.ORB orb    = ...
org.omg.CORBA.Any a      = orb.create_any();
a.insert_short(SYNC_WITH_SERVER.value); // the value for that policy
try
{
    Policy p = orb.create_policy(SYNC_SCOPE_POLICY_TYPE.value, a);
    server-new = ServerHelper.narrow(server._set_policy_override (new Policy[]{
        SetOverrideType.ADD_OVERRIDE));
    server._release();

    // get the ORB's policy manager
    PolicyManager policyManager =
        PolicyManagerHelper.narrow(
            orb.resolve_initial_references("ORBPolicyManager"));
}
```

```

// set an ORB-wide policy
policyManager.set_policy_overrides( new Policy[]{ p },
                                   SetOverrideType.ADD_OVERRIDE);
}
catch (PolicyError e)
{
    throw new RuntimeException ("policy error: " + e);
}

```

The above is portable code that relies only on standardized CORBA APIs to create and set policies. Because this code is somewhat cumbersome to write, JacORB also allows you to simplify it by creating the Policy object directly via its constructor, as shown below. Note that this is non-portable code:

```

SomeCorbaType server = ...

Policy p = new org.jacorb.orb.policies.SyncScopePolicy
            (SYNC_WITH_TARGET.value);
server-new = ServerHelper.narrow(server._set_policy_override (new Policy[]{ p },
                                                            SetOverrideType.ADD_OVERRIDE));
server._release();

```

See the package `org.jacorb.orb.policies` to find out which constructors are defined for the individual policy types.

## 18.1 Sync Scope

The `SyncScopePolicy` specifies at which point a oneway invocation returns to the caller. (The policy is ignored for non-oneway invocations.) There are four possible values:

**SYNC\_NONE** The invocation returns immediately.

**SYNC\_WITH\_TRANSPORT** The invocation returns after the request has been passed to the transport layer.

**SYNC\_WITH\_SERVER** The server sends an acknowledgement back to the client when it has received the request, but before actually invoking the target. The client-side call blocks until this acknowledgement has been received.

**SYNC\_WITH\_TARGET** An ordinary reply is sent back by the server, after the target invocation has completed. The client-side call blocks until this reply has been received.

The default mechanism in JacORB is `SYNC_WITH_TRANSPORT`, since the call to the socket layer is a synchronous one. In order to implement `SYNC_NONE`, an additional thread is created on the fly which in turn calls the socket layer, while the client-side invocation returns after this thread has been created. Given this additional overhead, it is unlikely that `SYNC_NONE` yields a significant performance gain for the client, not even on a multiprocessor machine.

The default mechanism can be configured by setting the property `jacorb.default_sync_scope` to a value corresponding to one of the policy values shown above. None for `SYNC_NONE`, Transport for `SYNC_WITH_TRANSPORT`, Server for `SYNC_WITH_SERVER`, or Target for `SYNC_WITH_TARGET`. The preferred mechanism is to set the scope via an application policy, however this property may be useful if a global scope change is required in a deployed application where a coding change is not an option.

## 18.2 Timing Policies

For each CORBA request four different points in time can be specified:

**Request Start Time** the time after which the request may be delivered to its target

**Request End Time** the time after which the request may no longer be delivered to its target

**Reply Start Time** the time after which the reply may be delivered to the client

**Reply End Time** the time after which the reply may no longer be delivered to the client

Each of these points in time can be specified on a per-object level as a client-side override policy: RequestStartTimePolicy, RequestEndTimePolicy, ReplyStartTimePolicy, and ReplyEndTimePolicy (see below for concrete code examples).

Each of these policies specifies an absolute time, which means that they will usually have to be set again for each individual request. As a convenience, there are two additional policies that allow you to specify a relative time for Request End Time and Reply End Time; they are called RelativeRequestTimeoutPolicy and RelativeRoundtripTimeoutPolicy, respectively. These timeouts are simply more convenient ways for expressing these two times; before each individual invocation, the ORB computes absolute times from them (measured from the start of the invocation at the client side) and handles them just as if an absolute Request End Time or Reply End Time had been specified. We will therefore only discuss the four absolute timing policies below.

All of these policies apply to synchronous and asynchronous invocations alike.

Figure 18.1 shows how JacORB interprets the timing policies in the course of a single request.

- As soon as the ORB receives control (prior to marshaling), it converts any RelativeRequestTimeoutPolicy or RelativeRoundtripTimeoutPolicy to an absolute value, by adding the relative value to the current system time.
- The ORB then checks whether Request End Time or Reply End Time have already elapsed. If so, no invocation is made, and an `org.omg.CORBA.TIMEOUT` is thrown to the client.
- After the ORB has sent the request, it waits for a reply until Reply End Time has elapsed. If it receives no reply before that, the request is discarded and an `org.omg.CORBA.TIMEOUT` thrown to the client. (JacORB does not currently cancel the outstanding request, it simply discards the reply, should one arrive after the timeout has elapsed.)<sup>1</sup>

---

<sup>1</sup>Note that if there is no connection to the server yet, other timeouts are applied first, configured by the properties `jacorb.connection.client.connect_timeout` and `jacorb.retries`. If connection establishment fails, control does not return to the client until these timeouts have expired, even if this is later than Reply




Figure 18.1: Timing Policies in JacORB

- On the server side (before demarshaling), the ORB checks whether the Request End Time has already elapsed. If so, the request is not delivered to the target, and an `org.omg.CORBA.TIMEOUT` is thrown back to the client.
- Optionally, the server-side ORB may also check at this point whether the Reply End Time has already elapsed, and not actually invoke the target in this case (throwing back an `org.omg.CORBA.TIMEOUT` to the client as well). Since the Reply End Time would then be checked both on the client and the server side, this requires that the clocks on both machines are synchronized at least to the same order of magnitude as the timeout itself. This check is therefore off by default, and may be enabled by setting the property `jacorb.poa.check_reply_end_time` to “on”.
- If the request proceeds, the ORB waits until the Request Start Time has been reached, if one was specified, and has not already elapsed. After that, the request is delivered to the target.
- After the target invocation has returned, the ORB may optionally check whether the Reply End Time has now elapsed. Similar to the check prior to the target invocation, this check is also optional and controlled by the property `jacorb.poa.check_reply_end_time` (see discussion above). If the check is enabled, and the Reply End Time is found to have elapsed at this point, the ORB sends an `org.omg.CORBA.TIMEOUT` back to the client, rather than the actual reply.
- If the reply arrives at the client before Reply End Time has elapsed, the ORB waits until Reply Start Time has been reached, if one was specified, and has not already elapsed. After that, the reply is delivered back to the client.

The bottom line of this is that for a simple, per-invocation timeout, you should specify a RelativeRoundtripTimeoutPolicy.

---

End Time.

## Programming

In CORBA, points of time are specified to an accuracy of 100 nanoseconds, using values of struct `TimeBase::UtcT`. To allow easy manipulation of such values from Java, JacORB provides a number of static methods in `org.jacorb.util.Time`. For example, to convert the current Java time into a `UtcT` value, write

```
UtcT currentTime = org.jacorb.util.Time.corbaTime();
```

To create a `UtcT` value that specifies a time  $n$  milliseconds in the future, you can write

```
UtcT time = org.jacorb.util.Time.corbaFuture (10000 * n);
```

(The argument to `corbaFuture()` is in CORBA time units of 100 ns; we multiply  $n$  by 10000 here to convert it from Java time units (milliseconds).)

The following shows how to set a timing policy for an object using the standard mechanism (see the beginning of this chapter for an explanation). In this example, we set a Reply End Time that lies one second in the future:

```
import org.omg.CORBA.*;

SomeCorbaType server = ... // the object for which we want to set
                          // a timing policy
org.omg.CORBA.ORB orb = ...
org.omg.CORBA.Any a = orb.create_any();

org.omg.TimeBase.UtcT replyEndTime
    = org.jacorb.util.Time.corbaFuture (1000 * 10000); // one second

org.omg.TimeBase.UtcTHelper.insert (a, replyEndTime);

try
{
    Policy p
        = orb.create_policy (REPLY_END_TIME_POLICY_TYPE.value, a);
    server-new = ServerHelper.narrow(server._set_policy_override (new Policy[]{
        SetOverrideType.ADD_OVERRIDE));
    server._release();
}
catch (PolicyError e)
{
    ...
}
```

Using the constructors of JacORB's implementations of policy values, this becomes less verbose:

```
SomeCorbaType server = ...

Policy p = new org.jacorb.orb.policies.ReplyEndTimePolicy
            (org.jacorb.util.Time.corbaFuture (1000 * 10000));

server-new = ServerHelper.narrow(server._set_policy_override (new Policy[]{ p },
                                                             SetOverrideType.ADD_OVERRIDE));

server._release();
```

Likewise, to set a Relative Roundtrip Timeout of one second, write:

```
SomeCorbaType server = ...

Policy p =
    new org.jacorb.orb.policies.RelativeRoundtripTimeoutPolicy
        (1000 * 10000);

server-new = ServerHelper.narrow(server._set_policy_override (new Policy[]{ p },
                                                             SetOverrideType.ADD_OVERRIDE));

server._release();
```

The difference between this and the example before, where a Reply End Time was used, is that the latter specifies a relative time to CORBA. The policy will therefore be valid for all subsequent invocations, because the absolute deadline will be recomputed before each invocation. In the first example, the deadline will no longer make sense for any subsequent invocations, since only an absolute time was specified to the ORB.

# 19 Connection Management and Connection Timeouts

JacORB offers a certain level of control over connections and timeouts. You can

- set connection idle timeouts.
- set request timing.
- set the maximum number of accepted TCP/IP connections on the server.

## 19.1 Timeouts

Connection idle timeouts can be set individually for the client and the server. They control how long an idle connection, i.e. a connection that has no pending replies, will stay open. The corresponding properties are `jacorb.connection.client.idle.timeout` and `jacorb.connection.server.timeout` and take their values as milliseconds. If not set, connections will stay open indefinitely (or until the OS decides to close them).

Request timing controls how long an individual request may take to complete. The programmer can specify this using QoS policies, discussed in chapter 18.

## 19.2 Connection Management

When a client wants to invoke a remote object, it needs to send the request over a connection to the server. If the connection isn't present, it has to be created. In JacORB, this will only happen once for every combination of host name and port. Once the connection is established, all requests and replies between client and server will use the same connection. This saves resources while adding a thin layer of necessary synchronization, and is the recommended approach of the OMG. Occasionally people have requested to allow for multiple connections to the same server, but nobody has yet presented a good argument that more connections would speed up things considerably.

Connections are typically blocking, with a separate thread used to handle sending and receiving data and managing time-outs. In cases of heavy load where the client may connect to dozens or hundreds of servers, and is using timeouts, this behavior can lead to very poor performance due to thread thrashing. To avoid this problem, JacORB 3.0.0 now makes available a non blocking mode for client side connections. Enabling this feature causes the client to use non-blocking connection establishment, sending of requests

and receiving replies. In this mode, the client uses a single thread or possibly a small pool of threads to wait for many connections to be ready for reading or writing.

Nonblocking I/O is currently only available for handling client side connections using plain IIOP. Server side support for receiving requests and sending replies is not yet available. Integration of SSL is also not available at this time.

On the server side, the property `jacorb.connection.max_server_connection` allows to set the maximum number of TCP/IP connections that will be listened on for requests. When using a network sniffer or tools like `netstat`, more inbound TCP/IP connections than the configured number may be displayed. This is for the following reason: Whenever the connection limit is reached, JacORB tries to close existing idle connections (see the subsection below). This is done on the thread that accepts the new connections, so JacORB will not actively accept more connections. However, the `ServerSocket` is initialized with a backlog of 20. This means that 20 more connections will be quasi-accepted by the OS. Only the 21st will be rejected right away.

## 19.2.1 Basics and Design

Whenever there is the need to close an existing connection because of the connection limit, the question arises on which of the connection to close. To allow for maximum flexibility, JacORB provides the interface `SelectionStrategy` that allows for a custom way to select a connection to close. Because selecting a connection usually requires some sort of statistical data about it, the interface `StatisticsProvider` allows to implement a class that collects statistical data.

```
package org.jacorb.orb.giop;

public interface SelectionStrategy
{
    public ServerGIOPConnection
        selectForClose( java.util.List connections );
}

public interface StatisticsProvider
{
    public void messageChunkSent( int size );
    public void flushed();
    public void messageReceived( int size );
}
```

The interface `SelectionStrategy` has only the single method of `selectForClose()`. This is called by the class `GIOPConnectionManager` when a connection needs to be closed. The argument is a `List` containing objects of type `ServerGIOPConnection`. The call itself is synchronized in the `GIOPConnectionManager`, so no additional synchronization has to be done by the implementor of `SelectionStrategy`. When examining the connections, the strategy can get hold of the `StatisticsProvider` via the method `getStatisticsProvider()` of the class



`GIOPConnection`. The strategy implementor should take care only to return idle connections. While the connection state is checked anyway while closing (it may have changed in the meantime), it seems to be more efficient to avoid cycling through the connections. When no suitable connection is available, the strategy may return `null`. The `GIOPConnectionManager` will then wait for a configurable time, and try again. This goes on until a connection can be closed.

The interface `StatisticsProvider` is used to collect statistical data about a connection and provide it to the `SelectionStrategy`. Because the nature of this data may vary, there is no standard access to the data via the interface. Therefore, `StatisticsProvider` and `SelectionStrategy` usually need to be implemented together. Whenever a new connection is created<sup>1</sup>, a new `StatisticsProvider` object is instantiated and stored with the `GIOPConnection`<sup>2</sup>. The `StatisticsProvider` interface is oriented along the mode of use of the `GIOPConnection`. For efficiency reasons, messages are not sent as one big byte array. Instead, they are sent piecewise over the wire. When such a chunk is sent, the method `messageChunkSent(int size)` will be called. After the message has been completely sent, method `flush()` is called. This whole process is synchronized, so all consecutive `messageChunkSents` until a `flush()` form a single message. Therefore, no synchronization on this level is necessary. However, access to gathered statistical data by the `SelectionStrategy` is concurrent, so care has to be taken. Receiving messages is done only on the whole, so there exists only one method, `messageReceived(int size)`, to notify the `StatisticsProvider` of such an event.

JacORB comes with two pre-implemented strategies: least frequently used and least recently used. LFU and LRU are implemented by the classes `org.jacorb.orb.giop.L[F|R]USelectionStrategyImpl` and `org.jacorb.orb.giop.L[F|R]UStatisticsProviderImpl`.

## 19.2.2 Configuration

To configure connection management, the following properties are provided:

`jacorb.connection.max_server_connections` This property sets the maximum number of TCP/IP connections that will be listened on by the server-side ORB.

`jacorb.connection.wait_for_idle_interval` This property sets the interval to wait until the next try is made to find an idle connection to close. Value is in microseconds.

`jacorb.connection.selection_strategy_class` This property sets the `SelectionStrategy`.

`jacorb.connection.statistics_provider_class` This property sets the `StatisticsProvider`.

`jacorb.connection.delay_close` If turned on, JacORB will delay closing of TCP/IP connections to avoid certain situations, where message loss can occur. See also section [19.2.3](#).

`jacorb.connection.nonblocking` Enables the use of NIO for client side connection management.

---

<sup>1</sup>Currently, connection management is only implemented for the server side. Therefore, only accepted `ServerGIOPConnections` will get a `StatisticsProvider`

<sup>2</sup>This is actually only done when a `StatisticsProvider` is configured

### 19.2.3 Limitations

When trying to close a connection, it is first checked that the connection is idle, i.e. has no pending messages. If this is the case, a GIOP CloseConnection message is sent, and the TCP/IP connection is closed. Under high load, this can lead to the following situation:

1. Server sends the CloseConnection message.
2. Server closes the TCP/IP connection.
3. The client sends a new request into the connection, because it hasn't yet read and acted on the CloseConnection message.
4. The server-side OS will send a TCP RST, which cancels out the CloseConnection message.
5. The client finds the connection closed and must consider the request lost.

To get by this situation, JacORB takes the following approach. Instead of closing the connection right after sending the CloseConnection message, we delay closing and wait for the client to close the connection. This behaviour is turned off by default, but can be enabled by setting the property `jacorb.connection.delay_close` to "yes". When non-JacORB clients are used care has to be taken that these ORBs do actively close the connection upon receiving a CloseConnection message.

# 20 Extensible Transport Framework

The Extensible Transport Framework (ETF), which JacORB implements, allows you to plug in other transport layers besides the standard IIOP (TCP/IP) protocol<sup>1</sup>.

To use an alternative transport, you need to (a) implement it as a set of Java classes following the ETF specification, and (b) tell JacORB to use the new transport instead of (or alongside with) the standard IIOP transport. We cover both steps below.

## 20.1 Implementing a new Transport

The interfaces that an ETF-compliant transport must implement are described in the ETF specification, and there is thus no need to repeat that information here. JacORB's default IIOP transport, which is realized in the package `org.jacorb.orb.iiop`, can also serve as a starting point for implementing your own transports.

For each transport, the following interfaces must be implemented (defined in `ETF.idl`, the package is `org.omg.ETF`):

**Profile** encapsulates addressing information for this transport

**Listener** server-side communication endpoint, waits for incoming connections and passes them up to the ORB

**Connection** an actual communication channel for this transport

**Factories** contains factory methods for the above interfaces

The `Handle` interface from the ETF package is implemented in the ORB (by the class `org.jacorb.orb.BasicAdapter`), not by individual transports. There is currently no support in JacORB for the optional zero-copy mechanism; the interface `ConnectionZeroCopy` therefore needn't be implemented.

On the server side, the `Listener` must pass incoming connections up to the ORB using the "Handle" mechanism; the `accept()` method needn't be implemented. Once a `Connection` has been passed up to the ORB, it will never be "returned" to the `Listener` again. The method `completed_data()` in the `Listener` interface therefore needn't be implemented, and neither should the `Listener` ever call `Handle.signal_data_available()` or `Handle.closed_by_peer()` (these methods throw a `NO_IMPLEMENT` exception in JacORB).

At the time of this writing (July 2003), there is still uncertainty in ETF about how server-specific

---

<sup>1</sup>At the time of this writing (July 2003), ETF is still a draft standard (OMG TC document mars/2003-02-01).

Profiles (as returned by `Listener.endpoint()`, for example) should be turned into object-specific ones for inclusion into IORs. We have currently added three new operations to the `Profile` interface to resolve this issue, see JacORB's version of `ETF.idl` for details.

## 20.2 Configuring Transport Usage

You tell JacORB which transports it should use by listing the names of their `Factories` classes in the property `jacorb.transport.factories`. In the standard configuration, this property contains only `org.jacorb.orb.iiop.IIOPFactories`, the `Factories` class for the standard IIOP transport. The property's value is a comma-separated list of fully qualified Java class names; each of these classes must be found somewhere on the CLASSPATH that JacORB is started with. For example:

```
jacorb.transport.factories = my.transport.Factories, org.jacorb.orb.iiop.IIOPFactories
```

By default, a JacORB server creates listeners for each transport listed in the above property, and publishes profiles for each of these transports in any IOR it creates. The order of profiles within an IOR is the same as that of the transports in the property.

If you don't want your servers to listen on each of these transports (e.g. because you want some of your transports only to be used for client-side connections), you can specify the set of actual listeners in the property `jacorb.transport.server.listeners`. The value of this property is a comma-separated list of numeric profile tags, one for each transport that you want listeners for, and which you want published in IOR profiles. The numeric value of a transport's profile tag is the value returned by the implementation of `Factories.profile_tag()` for that transport. Standard IIOP has profile tag 0 (`TAG_INTERNET_IOP`). Naturally, you can only specify profile tag numbers here for which you have a corresponding entry in `jacorb.transport.factories`.

So, to restrict your server-side transports to standard IIOP, you would write:

```
jacorb.transport.server.listeners = 0
```

On the client side, the ORB must decide which of potentially many transports it should use to contact a given server. The default strategy is that for each IOR, the client selects the first profile for which there is a transport implementation available at the client side (specified in `jacorb.transport.factories`). Profiles for which the client has no transport implementation are skipped.

Note that this is a purely static decision, based on availability of an implementation. JacORB does not attempt to actually establish a transport connection in order to find out which transport can be used. Also, should the selected transport fail, JacORB does not "fall back" to the next transport in the list. (This is because JacORB opens connections lazily, only when the first actual data is being sent.)

You can customize this strategy by providing your own implementation of `org.jacorb.orb.ProfileSelector`, and specifying it in the property `jacorb.transport.client.selector`. The interface `ProfileSelector` requires a single method,

```
public Profile selectProfile (List profiles,
                             ClientConnectionManager ccm);
```

For each IOR, this method receives a list of all profiles from the IOR for which the client has a transport implementation, in the order in which they appear in the IOR. The method should select one profile from this list and return it; this profile will then be used for communication with the server.

To help with the decision, JacORB's `ClientConnectionManager` is passed as an additional parameter. The method implementation can use it to check whether connections with a given transport, or to a given server, have already been made; it can also try and pre-establish a connection using a given transport and store it in the `ClientConnectionManager` for later use. (See the JacORB source code to find out how to deal with the `ClientConnectionManager`.)

The default `ProfileSelector` does not use the `ClientConnectionManager`, it simply returns the first profile from the list, unconditionally. To let JacORB use your own implementation of the `ProfileSelector` interface, specify the fully qualified classname in the property:

```
jacorb.transport.client.selector=my.pkg.MyProfileSelector
```

## 20.3 Selecting Specific Profiles Using RT Policies

JacORB has a implementation of the standard Real Time CORBA `ClientProtocolPolicy` policy which it uses to allow a developer to select between IIOP profiles that either support or do not support an SSL component. When applied to a bind (implicit or explicit), the `ClientProtocolPolicy` indicates the protocols that may be used to make a connection to the specified object.

The only non-standard proprietary component of this is the definition of two profile IDs that are used to distinguish between IIOP/SSL, IIOP/NOSSL and IIOP profiles. The three `org.omg.RTCORBA.Protocol` types are:

- `JAC_SSL_PROFILE_ID`
- `NOSSL_PROFILE_ID`
- `org.omg.IOP.TAG_INTERNET_IOP`

The former two are defined within `org.jacorb.orb.ORBConstants`. To apply this the developer may use, for example, a `ClientRequestInterceptor` that applies the policy to the object and throws a

ForwardRequest, or may simply apply the policy to the object as shown below.

```
org.omg.RTCORBA.Protocol protocol = new org.omg.RTCORBA.Protocol();
org.omg.RTCORBA.Protocol protocols[] = new org.omg.RTCORBA.Protocol[1];
org.omg.CORBA.Policy policies[] = new org.omg.CORBA.Policy[1];

protocol.protocol_type = ORBConstants.JAC_SSL_PROFILE_ID;
protocols[0] = protocol;

rtorb = org.omg.RTCORBA.RTORBHelper.narrow
        (orb.resolve_initial_references ("RTORB"));

org.omg.RTCORBA.ClientProtocolPolicy cpp =
        rtorb.create_client_protocol_policy (protocols);

policies[0] = cpp;

<mycorbaobject-two> = MyCorbaObjectHelper.narrow (<mycorbaobject>._set_policy
        (policies, SetOverrideType.SET_OVERRIDE));
<mycorbaobject>._release();
```

# 21 Security Attribute Service

The Security Attribute Service (SAS) is part of the Common Secure Interoperability Specification, Version 2 (CSIv2) CORBA specification. It is defined in the Secure Interoperability chapter (chapter 24) of the CORBA 3.0.2 Specification.

## 21.1 Overview

The SAS specification defines the interchange between a Client Security Service (CSS) and a Target Security Service (TSS) for the exchange of security authentication and authorization elements. This information is exchanged in the Service Context of the GIOP request and reply messages. The SAS may be used in conjunction with SSL to provide privacy of the messages being sent and received.

The SAS service is implemented as a series of standard CORBA interceptors, one for the CSS and one for the TSS. The service also uses a user specified SAS context class to support different authentication mechanisms, such as GSSUP and Kerberos.

The SAS service is activated based on entries in the JacORB properties file and CORBA Properties assigned to the POA.

The following is a part of the JacORB properties file that is used by the SAS.

```
#####
#
#   SAS configuration
#
#####

# Logger configuration
#jacorb.security.sas.log.verbosity=3
#jacorb.security.sas.GSSUP.log.verbosity=3
#jacorb.security.sas.TSS.log.verbosity=3
#jacorb.security.sas.CSS.log.verbosity=3
#jacorb.security.sas.Kerberos.log.verbosity=3

# This option defines the specific SAS context generator/validator
# Currently supported contexts include:
#   GssUpContext      - Uses GSSUP security
#   KerberosContext  - uses Kerberos security
# At least one context must be selected for SAS support
#jacorb.security.sas.contextClass=org.jacorb.security.sas.NullContext
jacorb.security.sas.contextClass=org.jacorb.security.sas.GssUpContext
#jacorb.security.sas.contextClass=org.jacorb.security.sas.KerberosContext

# This initializer installs the SAS interceptors
# Comment out this line if you do not want SAS support
```

```
org.omg.PortableInterceptor.ORBInitializerClass.SAS=org.jacorb.security.sas.SASInitializer

# Whether to support stateful contexts
# jacorb.security.sas.stateful=true

# Whether SSL is required.
#jacorb.security.sas.tss.requires_sas=false
```

## 21.2 GSSUP Example

The GSSUP (GSS Username/Password) example demonstrates the simplest usage of the SAS service. In this example, username and password pairs are sent via the SAS service. The client registers its username and password with the GSSUP Context which is later used CSS interceptor to generate the user's authentication information. The TSS retrieves the username and password without validating them. It is assumed by the TSS that the username and password are correct and/or will be further validated by a later interceptor or application code.

The following describes a SAS example using GSSUP.

### 21.2.1 GSSUP IDL Example

```
module demo{
  module sas{
    interface SASDemo{
      void printSAS();
    };
  };
};
```

The IDL contains a single interface. This interface is used to print out the user principal sent and received by the SAS service.

### 21.2.2 GSSUP Client Example

The following is a sample GSSUP client.

```
package demo.sas;

import java.io.BufferedReader;
import java.io.File;
import java.io.FileReader;

import org.jacorb.security.sas.GssUpContext;
import org.omg.CORBA.ORB;

public class GssUpClient {
  public static void main(String args[]) {
    if (args.length != 3) {
      System.out.println("Usage: java demo.sas.GssUpClient <ior_file> <username> <password>");
      System.exit(1);
    }
  }
}
```



```

    }
    try {
        // set security credentials
        GssUpContext.setUsernamePassword(args[1], args[2]);

        // initialize the ORB.
        ORB orb = ORB.init(args, null);

        // get the server
        File f = new File(args[0]);
        if (!f.exists()) {
            System.out.println("File " + args[0] + " does not exist.");
            System.exit(-1);
        }
        if (f.isDirectory()) {
            System.out.println("File " + args[0] + " is a directory.");
            System.exit(-1);
        }
        BufferedReader br = new BufferedReader(new FileReader(f));
        org.omg.CORBA.Object obj = orb.string_to_object(br.readLine());
        br.close();
        SASDemo demo = SASDemoHelper.narrow(obj);

        //call single operation
        demo.printSAS();
        demo.printSAS();
        demo.printSAS();

        System.out.println("Call to server succeeded");
    } catch (Exception ex) {
        ex.printStackTrace();
    }
}

```

The key to the client is the call to:

```
GssUpContext.setUsernamePassword(args[1], args[2]);
```

This call registers the client's username and password with the GSSUP context. This information will then later be used by the CSS interceptor as the user's authentication information.

### 21.2.3 GSSUP Target Example

The following is a sample GSSUP target.

```

package demo.sas;

import java.io.FileWriter;
import java.io.PrintWriter;

import org.jacorb.sasPolicy.SASPolicyValues;
import org.jacorb.sasPolicy.SAS_POLICY_TYPE;
import org.jacorb.sasPolicy.SASPolicyValuesHelper;
import org.omg.PortableServer.IdAssignmentPolicyValue;
import org.omg.PortableServer.LifespanPolicyValue;
import org.omg.PortableServer.POA;

```

```

import org.omg.CORBA.ORB;
import org.omg.CORBA.Any;
import org.omg.CSIOP.EstablishTrustInClient;

public class GssUpServer extends SASDemoPOA {

    private ORB orb;

    public GssUpServer(ORB orb) {
        this.ORB = orb;
    }

    public void printSAS() {
        try {
            org.omg.PortableInterceptor.Current current = (org.omg.PortableInterceptor.Current)orb
            org.omg.CORBA.Any anyName = current.get_slot(org.jacorb.security.sas.SASInitializer.s
            if( anyName.type().kind().value() == org.omg.CORBA.TCKind._tk_null ) {
                System.out.println("Null Name");
            } else {
                String name = anyName.extract_string();
                System.out.println("printSAS for user " + name);
            }
        } catch (Exception e) {
            System.out.println("printSAS Error: " + e);
        }
    }

    public static void main(String[] args) {
        if (args.length != 1) {
            System.out.println("Usage: java demo.sas.GssUpServer <ior_file>");
            System.exit(-1);
        }

        try {
            // initialize the ORB and POA.
            ORB orb = ORB.init(args, null);
            POA rootPOA = (POA) orb.resolve_initial_references("RootPOA");
            org.omg.CORBA.Policy [] policies = new org.omg.CORBA.Policy[3];
            policies[0] = rootPOA.create_id_assignment_policy(IdAssignmentPolicyValue.USER_ID);
            policies[1] = rootPOA.create_lifespan_policy(LifespanPolicyValue.PERSISTENT);
            Any sasAny = orb.create_any();
            SASPolicyValuesHelper.insert( sasAny, new SASPolicyValues(EstablishTrustInClient.value
            policies[2] = orb.create_policy(SAS_POLICY_TYPE.value, sasAny);
            POA securePOA = rootPOA.create_POA("SecurePOA", rootPOA.the_POAManager(), policies);
            rootPOA.the_POAManager().activate();

            // create object and write out IOR
            GssUpServer server = new GssUpServer(orb);
            securePOA.activate_object_with_id("SecureObject".getBytes(), server);
            org.omg.CORBA.Object demo = securePOA.servant_to_reference(server);
            PrintWriter pw = new PrintWriter(new FileWriter(args[0]));
            pw.println(orb.object_to_string(demo));
            pw.flush();
            pw.close();

            // run the ORB
            orb.run();
        } catch (Exception e) {
            e.printStackTrace();
        }
    }
}

```

## 21.3 Kerberos Example

The Kerberos example demonstrates how to integrate the use of a kerberos service to provide authentication credentials to the SAS service. In this example, the Java(TM) Authentication and Authorization Service (JAAS) is used to perform the Kerberos login and to return the principal and Kerberos ticket. The actual username and password may either be entered by the user or derived from the current user's Kerberos login session. For Windows 2000 Active Directory networks, this means that the user's credentials can be automatically obtained from the Windows login.

The following describes a SAS example using Kerberos.

### 21.3.1 Kerberos IDL Example

```
module demo{
  module sas{
    interface SASDemo{
      void printSAS();
    };
  };
};
```

The IDL contains a single interface. This interface is used to print out the user principal sent and received by the SAS service.

### 21.3.2 Kerberos Client Example

The following is a sample Kerberos client.

```
package demo.sas;

import java.io.BufferedReader;
import java.io.File;
import java.io.FileReader;
import java.security.Principal;
import java.security.PrivilegedAction;

import javax.security.auth.Subject;
import javax.security.auth.login.LoginContext;
import javax.security.auth.login.LoginException;

import org.omg.CORBA.ORB;

public class KerberosClient {
  private static Principal myPrincipal = null;
  private static Subject mySubject = null;
  private static ORB orb = null;

  public KerberosClient(String args[]) {

    try {
      // initialize the ORB.
      orb = ORB.init(args, null);
    }
  }
}
```

```

// get the server
File f = new File(args[0]);
if (!f.exists()) {
    System.out.println("File " + args[0] + " does not exist.");
    System.exit(-1);
}
if (f.isDirectory()) {
    System.out.println("File " + args[0] + " is a directory.");
    System.exit(-1);
}
BufferedReader br = new BufferedReader(new FileReader(f));
org.omg.CORBA.Object obj = orb.string_to_object(br.readLine());
br.close();
SASDemo demo = SASDemoHelper.narrow(obj);

//call single operation
demo.printSAS();
demo.printSAS();
demo.printSAS();

System.out.println("Call to server succeeded");
} catch (Exception ex) {
    ex.printStackTrace();
}
}

public static void main(String args[]) {
    if (args.length != 3) {
        System.out.println("Usage: java demo.sas.KerberosClient <ior_file> <username> <password>");
        System.exit(1);
    }

    // login - with Kerberos
    LoginContext loginContext = null;
    try {
        JaasTxtCallbackHandler txtHandler = new JaasTxtCallbackHandler();
        txtHandler.setMyUsername(args[1]);
        txtHandler.setMyPassword(args[2].toCharArray());
        loginContext = new LoginContext("KerberosClient", txtHandler);
        loginContext.login();
    } catch (LoginException le) {
        System.out.println("Login error: " + le);
        System.exit(1);
    }
    mySubject = loginContext.getSubject();
    myPrincipal = (Principal) mySubject.getPrincipals().iterator().next();
    System.out.println("Found principal " + myPrincipal.getName());

    // run in privileged mode
    final String[] finalArgs = args;
    try {
        Subject.doAs(mySubject, new PrivilegedAction() {
            public Object run() {
                try {
                    KerberosClient client = new KerberosClient(finalArgs);
                    orb.run();
                } catch (Exception e) {
                    System.out.println("Error running program: "+e);
                }
                System.out.println("Exiting privileged operation");
                return null;
            }
        });
    } catch (Exception e) {
        System.out.println("Error running privileged: "+e);
    }
}

```

```

    }
}

```

The CSS uses JAAS to logon and return the user's Kerberos credentials. The CSS must then run the rest of the application as a PrivilegedAction using the logged on credentials. This allows the CSS interceptor to retrieve the Kerberos ticket from the logon session.

The following is the JAAS logon configuration for the CSS:

```

KerberosClient
{
    com.sun.security.auth.module.Krb5LoginModule required storeKey=true useTicketCache=true debug=true;
};

```

### 21.3.3 Kerberos Target Example

The following is a sample Kerberos target.

```

package demo.sas;

import java.io.FileWriter;
import java.io.PrintWriter;
import java.security.Principal;
import java.security.PrivilegedAction;

import javax.security.auth.Subject;
import javax.security.auth.login.LoginContext;
import javax.security.auth.login.LoginException;

import org.jacorb.sasPolicy.SASPolicyValues;
import org.jacorb.sasPolicy.SAS_POLICY_TYPE;
import org.jacorb.sasPolicy.SASPolicyValuesHelper;
import org.omg.PortableServer.IdAssignmentPolicyValue;
import org.omg.PortableServer.LifespanPolicyValue;
import org.omg.PortableServer.POA;
import org.omg.CORBA.ORB;
import org.omg.CORBA.Any;
import org.omg.CSIIOP.EstablishTrustInClient;

public class KerberosServer extends SASDemoPOA {
    private static Principal myPrincipal = null;
    private static Subject mySubject = null;
    private ORB orb;

    public KerberosServer(ORB orb) {
        this.ORB = orb;
    }

    public void printSAS() {
        try {
            org.omg.PortableInterceptor.Current current = (org.omg.PortableInterceptor.Current) orb.
            org.omg.CORBA.Any anyName = current.get_slot(org.jacorb.security.sas.SASInitializer.s
            String name = anyName.extract_string();
            System.out.println("printSAS for user " + name);
        } catch (Exception e) {
            System.out.println("printSAS Error: " + e);
        }
    }
}

```

```

}

public KerberosServer(String[] args) {
    try {
        // initialize the ORB and POA.
        orb = ORB.init(args, null);
        POA rootPOA = (POA) orb.resolve_initial_references("RootPOA");
        org.omg.CORBA.Policy [] policies = new org.omg.CORBA.Policy[3];
        policies[0] = rootPOA.create_id_assignment_policy(IdAssignmentPolicyValue.USER_ID);
        policies[1] = rootPOA.create_lifespan_policy(LifespanPolicyValue.PERSISTENT);
        Any sasAny = orb.create_any();
        SASPolicyValuesHelper.insert( sasAny, new SASPolicyValues(EstablishTrustInClient.value));
        policies[2] = orb.create_policy(SAS_POLICY_TYPE.value, sasAny);
        POA securePOA = rootPOA.create_POA("SecurePOA", rootPOA.the_POAManager(), policies);
        rootPOA.the_POAManager().activate();

        // create object and write out IOR
        securePOA.activate_object_with_id("SecureObject".getBytes(), this);
        org.omg.CORBA.Object demo = securePOA.servant_to_reference(this);
        PrintWriter pw = new PrintWriter(new FileWriter(args[0]));
        pw.println(orb.object_to_string(demo));
        pw.flush();
        pw.close();
    } catch (Exception e) {
        e.printStackTrace();
    }
}

public static void main(String[] args) {
    if (args.length != 2) {
        System.out.println("Usage: java demo.sas.KerberosServer <ior_file> <password>");
        System.exit(-1);
    }

    // login - with Kerberos
    LoginContext loginContext = null;
    try {
        JaasTxtCallbackHandler cbHandler = new JaasTxtCallbackHandler();
        cbHandler.setMyPassword(args[1].toCharArray());
        loginContext = new LoginContext("KerberosService", cbHandler);
        loginContext.login();
    } catch (LoginException le) {
        System.out.println("Login error: " + le);
        System.exit(1);
    }

    mySubject = loginContext.getSubject();
    myPrincipal = (Principal) mySubject.getPrincipals().iterator().next();
    System.out.println("Found principal " + myPrincipal.getName());

    // run in privileged mode
    final String[] finalArgs = args;
    try {
        Subject.doAs(mySubject, new PrivilegedAction() {
            public Object run() {
                try {
                    // create application
                    KerberosServer app = new KerberosServer(finalArgs);
                    app.ORB.run();
                } catch (Exception e) {
                    System.out.println("Error running program: "+e);
                }
                return null;
            }
        });
    } catch (Exception e) {

```

```
        System.out.println("Error running privileged: "+e);
    }
}
```

The TSS uses JAAS to logon and return the user's Kerberos credentials. The logon principal to use is defined in the JAAS login configuration file. The TSS must then run the rest of the application as a PrivilegedAction using the logged on credentials. This allows the TSS interceptor to retrieve the Kerberos ticket from the logon session.

The following is the JAAS logon configuration for the TSS:

```
KerberosService
{
    com.sun.security.auth.module.Krb5LoginModule required storeKey=true principal="testService@OPENROADSCONSU
};
```





# 22 The JacORB Notification Service

The JacORB Notification Service is a partial implementation of the Notification Service specified by the OMG.

## 22.1 Unsupported Features

The JacORB Notification Service does not support persistent connections or events.

## 22.2 Installation

## 22.3 Running the Notification Service

Before the JacORB Notification Service can be accessed, a server process must be started. Starting the notification server is done by running

```
$ ntfy [-printIOR] [-printCorbaloc] [-writeIOR filename]  
[-registerName nameID [.nameKind]] [-port oaPort] [-channels channels]  
[-help]
```

-printIOR	print the IOR to STDOUT
-printCorbaloc	print the Corbaloc to STDOUT
-writeIOR <u>filename</u>	write the IOR to a file
-registerName <u>nameID</u> [ <u>.nameKind</u> ]	make a Name Service entry for the EventChannelFactory. The Notification Service will resolve the Name Service by invoking <code>resolve_initial_references("NameService").</code> Ensure that your environment is set up properly.
-port <u>oaport</u>	start the Notification Service on the specified port.
-channels <u>channels</u>	create a number of EventChannels.

### 22.3.1 Running as a NT Service or an UNIX Daemon

With a little help from [the Java Service Wrapper](#) it is easy to run the JacORB notification service as a NT Service or as an UNIX daemon.

#### Installing and Running as a NT Service

The necessary wrapper configuration files are located in the `JacORB/bin` directory.

The notification service can be installed as a NT service by double clicking on the `NotifyService-Install-NT.bat` batch file which is located in the `JacORB/bin` directory. Alternatively you can open a Command Window and then run the install script from the command prompt.

```
C:\JacORB\bin>NotifyService-Install-NT.bat
wrapper | JacORB Notification Service installed.
```

Once the service has been installed, it can be started by opening up the Service Control Panel, selecting the service, and then pressing the start button.

The service can also be started and stopped from within a Command Window by using the `net start JacORB-Notify` and `net stop JacORB-Notify` commands, or by passing commands to the `wrapper.exe` executable.

The wrapper is set up to start the JacORB Notification Service whenever the machine is rebooted. The service can be uninstalled by running the `NotifyService-Uninstall-NT.bat` batch file. See the Windows specific [wrapper documentation](#) for more details.

#### Installing and Running as an UNIX Daemon

JacORB is shipped with a `sh` script which can be used to start and stop the JacORB Notification Service controlled by the Java Service Wrapper.

First you need to download the appropriate binary for your system from <http://wrapper.tanukisoftware.org>. The Java Service Wrapper is supported on Windows, Linux, Solaris, AIX, HP-UX, Macintosh OS X, DEC OSF1, FreeBSD, and SGI Irix systems (Note: You don't need to download anything if you are running Windows. All necessary stuff is shipped with the JacORB distribution).

Install the Java Service Wrapper to a appropriate place by unzipping it (`WRAPPER_HOME`). Add `WRAPPER_HOME/bin` to your `PATH` variable. If you don't want to modify your `PATH` variable you can put a link to `WRAPPER_HOME/bin/wrapper` in one of the directories that's already in your `PATH` environment (e.g. `ln -s /usr/local/wrapper/bin/wrapper /usr/local/bin`).

Ensure that the shell-script `JacORB/bin/ntfy-wrapper` has the executable bit set. Note that the `.sh` script will attempt to create a `pid` file in the directory specified by the property `PIDDIR` in the script. If the user used to launch the Wrapper does not have permission to write to this directory then this will result in an error. An alternative that will work in most cases is to write the `pid` file to another directory. To make this change, edit the `.sh` script and change the following setting:

```
PIDDIR="."
```

to something more appropriate:

```
PIDDIR="/var/run"
```

**Running in the console** The JacORB notification service can now be run by simply executing `bin/ntfy-wrapper console`. When running using the console command, output from the notification service will be visible in the console. The notification service can be terminated by hitting CTRL-C in the command window. This will cause the Wrapper to shut down the service cleanly.

If you omit the command the script prints the available commands. The script accepts the commands `start`, `stop`, `restart` and `dump`. The `start`, `stop`, and `restart` commands are common to most daemon scripts and are used to control the wrapper and the notification service as a daemon process. The console command will launch the wrapper in the current shell, making it possible to kill the application with CTRL-C. Finally the command `dump` will send a `kill -3` signal to the wrapper causing its JVM to do a full thread dump.

**Running as a Daemon Process** The application can be run as a detached daemon process by executing the script using the `start` command.

When running using the `start` command, output from the JVM will only be visible by viewing the logfile `NotifyService-Wrapper.log` using `tail -f NotifyService-Wrapper.log`. The location of the logfile can be configured in the wrapper configuration file `bin/NotifyService-Wrapper.conf`

Because the application is running as a detached process, it can not be terminated using CTRL-C and will continue to run even if the console is closed.

To stop the application rerun the script using the `stop` command.

**Installing The Notification Service To Start on Reboot** This is system specific. See the UNIX specific [wrapper documentation](#) for instructions for some platforms.

## 22.3.2 Running as a JBoss Service

The JacORB notification service can also be run as a jboss service.

As first step the `jacorb.jar` that is shipped with jboss (`JBOSS_HOME/server/all/lib`) needs to be replaced to the current version (v2.2.3). As next step the `jboss-cosnotification.sar` file can be deployed into jboss by copying it to `JBOSS_HOME/server/all/deploy`.

After starting jboss a mbean for the notification service will show up in the jboss jmx management console.

## 22.4 Accessing the Notification Service

Configuring a default notification service as the ORB's default is done by adding the URL that points to the service to the properties files `.jacorb.properties`. A valid URL can be obtained in various ways:

1. By specifying the option `-printIOR` as you start the notification service a stringified IOR is printed out to the console. From there you can copy it to a useful location.
2. Usually the stringified IOR makes most sense inside a file. Use the option `-writeIOR <filename>` to write the IOR to the specified file.
3. A more compact URL can be obtained by using the option `-printCorbaloc`. In conjunction with the option `-port` you can use the simplified corbaloc: URL of the form `corbaloc::ip-address:port/NotificationService`. This means all you need to know to construct an object reference to your notification service is the IP address of the machine and the port number the server process is listening on (the one specified using `-port`).

Add the property `ORBInitRef.NotificationService` to your properties file. The value can be a corbaloc: URL or alternatively the file name where you saved the IOR.

The JacORB notification service is accessed using the standard CORBA defined interface:

```
// get a reference to the notification service
ORB orb = ORB.init(args, null);
org.omg.CORBA.Object obj;
obj = orb.resolve_initial_references("NotificationService");
EventChannelFactory ecf = EventChannelFactoryHelper.narrow( o );
IntHolder ih = new IntHolder();
Property[] p1 = new Property[0];
Property[] p2 = new Property[0];
EventChannel ec = ecf.create_channel(p1, p2, ih);
...
```

## 22.5 Configuration

Following is a brief description of the properties that control Notification Service behaviour.

The Notification Service uses up to three Thread Pools with a configurable size. The first Thread Pool is used to process the filtering of the Messages. The second Thread Pool is used to deliver the Messages to the Consumers. The third Thread Pool is used to pull Messages from PullSuppliers.

Table 22.1: Notification Service Properties

Property	Description	Type	Default
----------	-------------	------	---------

Table 22.1: Notification Service Properties

Property	Description	Type	Default
<code>filter.thread_pool_size</code> <sup>1</sup>	This is the Size of the Thread Pool used to process the filters. Increasing this value on a Multiprocessor machine or if Filters are on a different machine than the Channel could increase the Filtering Performance as multiple events can be processed concurrently.	<code>int ≥ 0</code>	2
<code>proxysupplier.thread_pool_size</code>	This is the Size of the Thread Pool used to deliver the Messages to the Consumers. By using the property <code>proxysupplier.threadpolicy</code> <sup>2</sup> it is also possible to use one Thread per ProxySupplier.	<code>int ≥ 0</code>	4
<code>proxyconsumer.thread_pool_size</code>	Specifies the Size of the Thread Pool used to pull Messages from PullSuppliers	<code>int ≥ 0</code>	2
<code>proxysupplier.threadpolicy</code>	Specify which thread policy the ProxySuppliers should use to deliver the Messages to its Consumers. Valid values are:  <b>ThreadPool</b> a fixed number of threads is used. See property <code>proxysupplier.thread_pool_size</code> .  <b>ThreadPerProxy</b> Each ProxySupplier uses its own thread.	string	Thread-Pool
<code>supplier.poll_intervall</code>	Specifies how often Messages should be pulled from a PullSupplier. The value specifies the intervall between two pull-Operations.	milli-seconds	1000
<code>supplier.max_number</code>	Specify the maximum number of Suppliers that may be connected to a Channel at a time. If a Supplier tries to connect, while this limit is exceeded, <code>AdminLimitExceeded</code> is raised. Note that this property can also be set programatically via the <code>set_admin</code> operation.	<code>int &gt; 0</code>	maximum int value

<sup>1</sup>All notification service properties share the common prefix `jacorb.notification` which is omitted here to save some space

<sup>2</sup>also abbreviated.

Table 22.1: Notification Service Properties

Property	Description	Type	Default
<code>consumer_max_number</code>	Specify the maximum number of Consumers that may be connected to a Channel at a time. If a Consumer tries to connect, while this limit is exceeded, <code>AdminLimitExceeded</code> is raised. Note that this property can also be set programatically via the <code>set_admin</code> operation.	<code>int &gt; 0</code>	maximum int value
<code>max_events_per_consumer</code>	Specifies how many Events a ProxySupplier at most should queue for a consumer. If this number is exceeded Events are discarded according to the <code>DiscardPolicy</code> configured for the ProxySupplier.	<code>int &gt; 0</code>	100
<code>max_batch_size</code>	Specifies the maximal number of Messages a SequencePushSupplier should queue before a delivery to its connected SequencedPushConsumer is forced.	<code>int &gt;= 0</code>	1
<code>order_policy</code>	Specify how events that are queued should be ordered. Valid values are: <ul style="list-style-type: none"> <li>• AnyOrder</li> <li>• PriorityOrder</li> <li>• DeadlineOrder</li> <li>• FifoOrder</li> </ul>	string	Priority-Order
<code>discard_policy</code>	Specifies which Events are discarded if more than the maximal number of events are queued for a consumer. Valid values are: <ul style="list-style-type: none"> <li>• AnyOrder</li> <li>• PriorityOrder</li> <li>• DeadlineOrder</li> <li>• FifoOrder</li> <li>• LifoOrder</li> </ul>	string	Priority-Order
<code>consumer.backout_interval</code>	After a delivery to a Consumer has failed the Channel will pause delivery to that Consumer for a while before retrying. This property specifies how long a consumer should stay disabled.	milli-seconds	1000

Table 22.1: Notification Service Properties

Property	Description	Type	Default
<code>consumer.error_threshold</code>	Each failed delivery to a consumer increments an errorcounter. If this errorcounter exceeds the specified value the consumer is disconnected from the channel.	int $\geq$ 0	3
<code>default_filter_factory</code>	Specify which <code>FilterFactory</code> ( <code>CosNotifyFilter::FilterFactory</code> ) the attribute <code>EventChannel::default_filter_factory</code> should be set to. Default value is <code>builtin</code> . This special value implies that a <code>FilterFactory</code> will be created during start of the <code>EventChannel</code> . Its possible to set this property to a URL that points to another <code>CosNotifyFilter::FilterFactory</code> object. In this case no <code>FilterFactory</code> is started by the <code>EventChannel</code> . The URL is resolved by a call to <code>ORB::string_to_object</code> .	URL	builtin
<code>proxy.destroy_causes_disconnect</code>	Specify if a destroyed Proxy should call the disconnect operation of its consumer/supplier.	boolean	on

### 22.5.1 Setting up Bidirectional GIOP

If you have set the `ORBInitializer` property as described in Section 15.1.1 the Notification will automatically configure its POA to use Bidirectional GIOP.

## 22.6 Monitoring the Notification Service

The JacORB Notification Service provides JMX MBean interfaces which make it possible to monitor and control the Service using a JMX console. This section will describe how to start a JMX enabled Notification Service and how to configure your JMX console to access the exposed MBeans.

### 22.6.1 Download MX4J

MX4J is an Open Source implementation of the JMX specification. You need to download the current release of MX4J (currently 3.0.1) from the JMX project page [mx4j.sourceforge.net](http://mx4j.sourceforge.net) and install MX4J in an appropriate place.

## 22.6.2 Edit Java Service Wrapper configuration

The configuration file `NotifyService-Wrapper-MX4J.conf.template` contains the necessary settings to start the JMX enabled Notification Service. You have to edit the classpath. Replace the token `@MX4J_HOME@` with the concrete path to your MX4J installation.

```
# Java Classpath (include wrapper.jar) Add class path elements as
# needed starting from 1
wrapper.java.classpath.1=../lib/wrapper-3.x.y.jar
...
wrapper.java.classpath.8=@MX4J_HOME@/lib/mx4j.jar
wrapper.java.classpath.9=@MX4J_HOME@/lib/mx4j-remote.jar
wrapper.java.classpath.10=@MX4J_HOME@/lib/mx4j-tools.jar
```

After customization of the configuration file it must be renamed to `NotifyService-Wrapper.conf` as the start script reads its configuration from the so called file.

## 22.6.3 Start the Service

consult section [22.3.1](#) for further details to start the Service.

## 22.6.4 Connecting to the management console

The Notification Service web management console will be available at <http://localhost:8001>.

A JSR 160 RMI connector allows a management console to connect to the Notification Service. The Service URL is `service:jmx:rmi:///localhost/jndi/rmi:///localhost:1099/jndi/COSNotification`.

## 22.7 Extending the JacORB Notification Service

### 22.7.1 Adding custom Filters

The JacORB Notification Service supports the full ETCL filter grammar. If you need to use your own specialized filters you have to provide an implementation of the Filter Interface. You can extend the class `org/jacorb/notification/filter/AbstractFilter.java` that provides generic filter management. See the class `org/jacorb/notification/filter/bsh/BSHFilter.java` for an example of an [Beanshell](#) based custom filter. Additionally to the standard ETCL grammar the FilterFactory will try to load all filter grammars specified in `jacorb.properties`. An entry must have the following form: `jacorb.notification.filter.plugin.GRAMMAR=CLASSNAME` where `GRAMMAR` should be replaced by the name of the grammar and `CLASSNAME` should be replaced by the classname of the custom filter implementation.



---

custom filters can then be created by invoking `FilterFactory::create_filter` or `FilterFactory::create_mapping_filter` and specifying GRAMMAR as parameter.



## 23 Using Java management Extensions (JMX)

This section describes how to use the Java Management Extension API along with JacORB to instrument both the orb and application that use JacORB.

### 23.1 MX4J and JMX over IIOP

This section describes how to instrument a JacORB application using the MX4J JMX implementation. MX4J is an open source JMX implementation available at <http://mx4j.sourceforge.net>. This section also shows how to use JMX over IIOP. This allows JMX to use an existing JacORB ORB for RMI communications and the JacORB Naming Service to register you JMX MBeanServer.

To setup the JVM environment, three system defines are necessary:

```
-Djava.naming.factory.initial=com.sun.jndi.cosnaming.CNCTXFactory
-Djava.naming.provider.url=corbaloc:iiop:localhost:9101/StandardNS/NameServer-POA/_root
-Djavax.rmi.CORBA.PortableRemoteObjectClass=org.jacorb.orb.rmi.PortableRemoteObjectDelegateImpl
```

The first system property tells the Java JNDI subsystem to use the CORBA Naming Service for its naming repository. The second property is a pointer to the JacORB Naming Service instance. The third property tells the Java Remote object system to use JacORB's Portable Remote Object implementation. This is required so that JacORB can associate an RMI object with a CORBA object on one of its POAs.

The sample code for creating a MBeanServer is shown below

```
// The MBeanServer to which the JMXConnectorServer will be registered in
jmxServer = MBeanServerFactory.createMBeanServer();

// The address of the connector
HashMap environment = new HashMap();
org.jacorb.orb.rmi.PortableRemoteObjectDelegateImpl.setORB(orb);
JMXServiceURL address = new JMXServiceURL("service:jmx:iiop://localhost/jndi/jmxSnmpTrapNotify");
JMXConnectorServer cntorServer = JMXConnectorServerFactory.newJMXConnectorServer(address,

// Add MBeans
jmxServer.registerMBean(trapReceiver, new ObjectName("TrapReceiver:counts=default"));

// Start the JMXConnectorServer
cntorServer.start();
```

The first line creates the MBeanServer. The next 4 lines creates the remote JMX connection. The "setORB()" call assigns a previously initialized ORB to the Remote Object delegate. All RMI over

IIOP communications will occur via this ORB. The "address" is the name of the MBeanServer as known in the Naming service. The portion after "/jndi/" is the Naming Service name. The next line registers a MBean with the MBeanServer. The last line starts the MBeanServer.

A JMX console may then be used to monitor the JacORB application. For example, MC4J (<http://mc4j.sourceforge.net>) may be used. When setting up a mc4j connection, use the connection type JSR160 and set the server URL to the name as registered in the JacORB naming service, such as "service:jmx:iiop://localhost/jndi/jmxSnmpTrapNotify".

# 24 Transport Current

Using the `org.jacorb.transport.Current` Feature

by Iliyan Jeliaskov

## 24.1 Scope and Context

There is no standard-mandated mechanism to facilitate obtaining statistical or pretty much any operational information about the network transport which the ORB is using. While this is a direct corollary of the CORBA's design paradigm which mandates hiding all this hairy stuff behind non-transparent abstractions, it also precludes effective ORB and network monitoring.

The `Transport::Current` feature intends to fill this gap by defining a framework for developing a wide range of solutions to this problem. It also provides a basic implementation for the most common case - the IIOP transport.

By definition, transport-specific information is available in contexts where the ORB has selected a `Transport`:

- Within Client-side interception points;
- Within Server-side interception points;
- Inside a Servant up-call

The implementation is based on a generic service-oriented framework, implementing the `Transport::Current` interface. It is an optional service, which can be dynamically loaded. This service makes the `Transport::Current` interface available through `orb->resolve_initial_references()`. The basic idea is simple - whenever a `Transport` is chosen by the ORB, the `Transport::Current` (or a protocol-specific derivative) will have access to that instance and be able to provide some useful information.

## 24.2 Programmer's Reference

Consider the following IDL interface to access transport-specific data.

```
module org
{
    module jacorb
```

```

{

module transport
{
    /// A type used to represent counters
    typedef unsigned long long CounterT;

    // Used to signal that a call was made outside the
    // correct invocation context.

    exception NoContext
    {
    };

    // The main interface, providing access to the Transport-specific
    // information (traits), available to the current thread of
    // execution.

    local interface Current
    {
        /// Transport ID, unique within the process.
        long id() raises (NoContext);

        /// Bytes sent/received through the transport.
        CounterT bytes_sent() raises (NoContext);
        CounterT bytes_received() raises (NoContext);

        /// Messages (requests and replies) sent/received using the current
        /// protocol.
        CounterT messages_sent() raises (NoContext);
        CounterT messages_received() raises (NoContext);

        /// The absolute time (milliseconds) since the transport has been
        /// open.
        TimeBase::TimeT open_since() raises (NoContext);
    };

};

};

};

```

As an example of a specialized `Transport::Current` is the `Transport::IIOP::Current`, which derives from `Transport::Current` and has an interface, described in the following IDL:

```
module org
{

    module jacobr
    {

        module transport
        {
            /// A type used to represent counters
            typedef unsigned long long CounterT;

            // Used to signal that a call was made outside the
            // correct invocation context.

            exception NoContext
            {
                };

            // The main interface, providing access to the Transport-specific
            // information (traits), available to the current thread of
            // execution.

            local interface Current
            {
                /// Transport ID, unique within the process.
                long id() raises (NoContext);

                /// Bytes sent/received through the transport.
                CounterT bytes_sent() raises (NoContext);
                CounterT bytes_received() raises (NoContext);

                /// Messages (requests and replies) sent/received using the current
                /// protocol.
                CounterT messages_sent() raises (NoContext);
                CounterT messages_received() raises (NoContext);

                /// The absolute time (milliseconds) since the transport has been
                /// open.
                TimeBase::TimeT open_since() raises (NoContext);
            };
        };
    };
};
```

```
};
```

## 24.3 User's Guide

The `org.jacorb.transport.Current` can be used as a base interface for a more specialized interfaces. However, it is not required that a more specialized `Current` inherits from it.

Typical, generic usage is shown in the `tests/regression/src/org/jacorb/test/transport/IIOPTester.java` test:

```
...
// Get the Current object.
Object tcobject =
    orb.resolve_initial_references ("JacOrbIIOPTransportCurrent");
Current tc = CurrentHelper.narrow (tcobject);

logger.info("TC: ["+tc.id()+"] from="+tc.local_host() +": "
    + tc.local_port() +", to="
    +tc.remote_host()+": "+tc.remote_port());

logger.info("TC: ["+tc.id()+"] sent="+tc.messages_sent ()
    + "("+tc.bytes_sent ()+") "
    + ", received="+tc.messages_received ()
    + "("+tc.bytes_received ()+")");
...
```

### 24.3.1 Configuration, Bootstrap, Initialization and Operation

To use the Transport Current features the framework must be loaded through the Service Configuration framework. For example, using something like this:

```
...
Properties serverProps = new Properties();

// We need the TC functionality
serverProps.put ("org.omg.PortableInterceptor.ORBInitializerClass.
    server_transport_current_interceptor",
    "org.jacorb.transport.TransportCurrentInitializer");

serverProps.put ("org.omg.PortableInterceptor.ORBInitializerClass.
    server_transport_current_iiop_interceptor",
    "org.jacorb.transport.IIOPTransportCurrentInitializer");

serverORB = ORB.init(new String[0], serverProps);
...
```



The ORB initializer registers the "JacORBIIOPTransportCurrent" name with the orb, so that it could be resolved via `orb->resolve_initial_references("JacORBIIOPTransportCurrent")`.

Note that any number of transport-specific Current interfaces may be available at any one time.



# 25 JacORB Utilities

In this chapter we briefly explain the executables that come with JacORB. These include the IDL-compiler, a utility to decode IORs and print their components, the JacORB name server, a utility to test a remote object's liveness, etc.

- The command `jaco org.jacorb.util.Diagnostic` may be run to output useful environmental debugging information as well as the JacORB version.

## 25.1 idl

The IDL compiler parses IDL files and maps type definitions to Java classes as specified by the OMG IDL/Java language mapping. For example, IDL interfaces are translated into Java interfaces, and typedefs, structs, const declarations etc. are mapped onto corresponding Java classes. Additionally, stubs and skeletons for all interface types in the IDL specification are generated.

(The IDL parser was generated with Scott Hudson's CUP parser generator. The LALR grammar for the CORBA IDL is in the file `org/jacorb/idl/parser.cup`.)

### Compiler Definitions

A number of preprocessor symbols are defined intrinsically by the IDL compiler:

```
JACORB
_PRE_3_0_COMPILER_
GIOP_1_1
GIOP_1_2
```

These symbols can be undefined by using the `-U` IDL compiler flag, although this is not recommended as some supplied idl files may no longer compile correctly.

### Compiler Options

```
-h | help          print help on compiler options
-v | version      print compiler version information
```

-d dir	root of directory tree for output (default: current directory)
-syntax	syntax check only, no code generation
-Dx	define preprocessor symbol x with value 1
-Dx=y	define preprocessor symbol x with value y
-Idir	set include path for idl files
-Usymbol	undefine preprocessor symbol
-W [1..4]	debug output level (default is 1)
-all	generate code for all IDL files, even included ones (default is off) If you want to make sure that for a given IDL no code will be generated even if this option is set, use the (proprietary) preprocessor directive <code>#pragma inhibit_code_generation</code> .
-forceOverwrite	generate Java code even if the IDL files have not changed since the last compiler run (default is off)
-ami_callback	generate AMI reply handlers and sendc methods (default is off). See chapter 17
-ami_polling	generate AMI poller and sendp methods (default is off). See chapter 17
-addbackend classname	classname as code generator
-backend classname	use classname as compiler (code generator) backend. If no generator is specified then it will default to simple file output. Custom generators must implement the interface <code>org.jacorb.idl.IDLTreeVisitor</code>
-i2jpackage x:a.b.c	replace IDL package name x by a.b.c in generated Java code (e.g. CORBA:org.omg.CORBA)
-i2jpackagefile filename	replace IDL package names using list from <code>filename</code> . Format as above.
-ir	generate extra information required by the JacORB Interface Repository (One extra file for each IDL module, and another additional file per IDL interface.) (default is off)
-cldc10	Generate J2ME/CLDC1.0 compliant stubs
-genEnhanced	Generate stubs with <code>toString&gt;equals</code> (only <code>StructType</code> )
-nofinal	generated Java code will contain no final class definitions, which is the default to allow for compiler optimizations.
-unchecked_narrow	use <code>unchecked_narrow</code> in generated code for IOR parameters in operations (default is off). Generated helper classes contain marshalling code which, by default, will try to narrow any object references to statically known interface type. This may involve remote invocations to test a remote object's type, thus incurring runtime overhead to achieve static type safety. The <code>-unchecked_narrow</code> option generates code that will not be statically type safe, but avoids remote tests of an object's type. If the type is not as expected, clients will experience <code>CORBA.BAD_OPERATION</code> exceptions at invocation time.
-noskel	disables generation of POA skeletons (e.g., for client-side use)
-nostub	disables generation of client stubs (for server-side use)
-diistub	generate DII-based client stubs (default is off)
-sloppy_forward	allow forward declarations without later definitions (useful only for separate compilation).

-sloppy_names	less strict checking of module name scoping (default: off) CORBA IDL has a number of name resolution rules that are stricter than necessary for Java (e.g., a struct member's name identifier must not equal the type name). The -sloppy_names option relaxes checking of these rules. Note that IDL accepted with this option will be rejected by other, conformant IDL compilers!
-sloppy_identifiers	permit illegal identifiers that differ in case (04-03-12:3.3.2) (default: off)
-permissive_rmic	tolerate dubious and buggy IDL generated by JDK's rmic stub generator (e.g., incorrectly empty inheritance clauses), includes -sloppy_names.
-generate_helper_compatibility	controls the compatibility level of the generated helper code. Valid values are: <b>deprecated</b> uses CORBA 2.3 API. this API version is part of the JDK. <b>portable</b> uses CORBA 2.4 API. the usage of this option mandates the use of the JacORB provided <code>org.omg.*</code> classes on the bootclasspath. This is the default. <b>jacorb</b> uses JacORB API. The generated helper code will contain references to JacORB classes. The helpers will use the CORBA 2.4 API but won't be portable anymore. There's no need to put the <code>org.omg.*</code> classes provided by JacORB on the bootclasspath.

## i2jpackage

The `-i2jpackage` switch can be used to flexibly redirect generated Java classes into packages. Using this option, any IDL scope `x` can be replaced by one (or more) Java packages `y`. Specifying `-i2jpackage X:a.b.c` will thus cause code generated for IDL definitions within a scope `x` to end up in a Java package `a.b.c`, e.g. an IDL identifier `X::Y::ident` will be mapped to `a.b.c.y.ident` in Java. It is also possible to specify a file containing these mappings using the `-i2jpackagefile` switch.

### Example 1

given the following IDL definition

```
struct MyStruct
{
    long value;
};
```

Invoking `idl` without the `i2jpackage` option will generate (along with other files) the java file `MyStruct.java`

```
/**
 * Generated from IDL struct "MyStruct".
 *
 * @author JacORB IDL compiler V 2.3, 18-Aug-2006
```

```

* @version generated at 07.12.2006 11:46:28
*/

public final class MyStruct
    implements org.omg.CORBA.portable.IDLEntity
{
    [...]
}

```

Note that the class does not contain a package definition.

The option `-i2jpackage :com.acme` will place any identifier without scope into the java package `com.acme`. Thus we get:

```

package com.acme;

/**
 * Generated from IDL struct "MyStruct".
 *
 * @author JacORB IDL compiler V 2.3, 18-Aug-2006
 * @version generated at 07.12.2006 11:46:28
 */

public final class MyStruct
    implements org.omg.CORBA.portable.IDLEntity
{
    [...]
}

```

## Example 2

```

module outer
{
    struct OuterStruct
    {
        long value;
    };

    module inner
    {
        struct InnerStruct
        {
            long value;
        };
    };
};

```

If you're not using the `i2jpackage` option, the IDL compiler will generate the classes `outer.OuterStruct` and `outer.inner.InnerStruct`.

Again using the `i2jpackage` it's possible to map IDL modules to different java packages. `$ idl -i2jpackage outer:com.acme.outer` will generate the classes `com.acme.outer.OuterStruct` and `com.acme.outer.inner.InnerStruct`.

`$ idl -idjpackage inner:com.acme.inner` will generate the classes `outer.OuterStruct` and `outer.com.acme.inner.InnerStruct`.

Note: See Section 10.4 if you intend to use the `i2jpackage` option in conjunction with the JacORB IfR and are using `#pragma` prefix statements in your IDL.

## Compiler Options

If one is building from Ant it is possible to invoke the compiler directly using the supplied Ant task, JacIDL. To add the taskdef add the following to the ant script:

```
<taskdef name="jacidl" classname="org.jacorb.idl.JacIDL"/>
```

The task supports all of the options of the IDL compiler.

Table 25.1: JacIDL Configuration

Attribute	Description	Required	Default
<code>srcdir</code>	Location of the IDL files	Yes	
<code>destdir</code>	Location of the generated java files	Yes	
<code>includes</code>	Comma-separated list of patterns of files that must be included; all files are included when omitted.	No	
<code>includesfile</code>	The name of a file that contains include patterns.	No	
<code>excludes</code>	Comma-separated list of patterns of files that must be excluded; files are excluded when omitted.	No	
<code>excludesfile</code>	The name of a file that contains include patterns.	No	
<code>defaultexcludes</code>	Indicates whether default excludes should be used (yes — no); default excludes are used when omitted.	No	
<code>includepath</code>	The path the idl compiler will use to search for included files.	No	
<code>parseonly</code>	Only perform syntax check without generating code.	No	False
<code>noskel</code>	Disables generation of POA skeletons	No	False
<code>nostub</code>	Disables generation of client stubs	No	False
<code>diistub</code>	Generate DII-based client stubs	No	False
<code>sloppyforward</code>	Allow forward declarations without later definitions	No	False
<code>sloppyname</code>	Less strict checking of names for backward compatibility	No	False
<code>generateir</code>	Generate information required by the Interface Repository	No	False

Table 25.1: JacIDL Configuration

Attribute	Description	Required	Default
all	Generate code for all IDL files, even included ones	No	False
nofinal	Generate class definitions that are not final	No	False
forceoverwrite	Generate code even if IDL has not changed.	No	False
uncheckedNarrow	Use unchecked_narrow in generated code for IOR parameters in operations.	No	False
ami	Generate ami callbacks.	No	False
debuglevel	Set the debug level from 0 to 4.	No	0
helpercompat	control the portability of the generated helper code.	No	portable

## Nested Elements

Several elements may be specified as nested elements. These are <define>, <undefine>, <include>, <exclude>, <patternset> and <i2jpackage>. The format of <i2jpackage> is <i2jpackage names="x:y">

## Examples

The task command

```
<jacidl destdir="${generate}"
      srcdir="${idl}"
/>
```

compiles all \*.idl files under the \$idl directory and stores the .java files in the \$generate directory.

```
<jacidl destdir="${generate}" srcdir="${idl}">
  <define key="GIOP_1_1" value="1"/>
</jacidl>
```

like above, but additionally defines the symbol GIOP\_1\_1 and sets its (optional) value to 1.

```
<jacidl destdir="${generate}"
      srcdir="${idl}"
      excludes="**/*foo.idl"
/>
```

like the first example, but exclude all files which end with foo.idl.



## 25.2 ns

JacORB provides a service for mapping names to network references. The name server itself is written in Java like the rest of the package and is a straightforward implementation of the CORBA “Naming Service” from Common Object Services Spec., Vol.1 [?]. The IDL interfaces are mapped to Java according to our Java mapping.

### Usage

```
$ ns <filename> [<timeout>]
```

or

```
$ jaco jacob.Naming.NameServer <filename> [<timeout>]
```

### Example

```
$ ns ~/public_html/NS_Ref
```

The name server does *not* use a well known port for its service. Since clients cannot (and need not) know in advance where the name service will be provided, we use a bootstrap file in which the name server records an object reference to itself (its *Interoperable Object Reference* or IOR). The name of this bootstrap file has to be given as an argument to the `ns` command. This bootstrap file has to be available to clients network-wide, so we demand that it be reachable via a URL — that is, there must be an appropriately configured HTTP server in your network domain which allows read access to the bootstrap file over a HTTP connection. (This implies that the file must have its read permissions set appropriately. If the binding to the name service fails, please check that this is the case.) After locating the name service through this mechanism, clients will connect to the name server directly, so the only HTTP overhead is in the first lookup of the server.

The name bindings in the server’s database are stored in and retrieved from a file that is found in the current directory unless the property `jacorb.naming.db_dir` is set to a different directory name. When the server starts up, it tries to read this file’s contents. If the file is empty or corrupt, it will be ignored (but overridden on exit). The name server can only save its state when it goes down after a specified timeout. If the server is interrupted (with `CTRL-C`), state information is lost and the file will not contain any usable data.

If no timeout is specified, the name server will simply stay up until it is killed. Timeouts are specified in milliseconds.

## 25.3 nmg

The JacORB NameManager, a GUI for the name service, can be started using the `nmg` command. The NameManager then tries to connect to an existing name service.

## Usage

```
$ nmg
```

## 25.4 lsns

This utility lists the contents of the default naming context. Only currently active servers that have registered are listed. The `-r` option recursively lists the contents of naming contexts contained in the root context. If the graph of naming contexts contains cycles, trying to list the entire contents recursively will not return...

## Usage

```
$ lsns [-r]
```

## Example

```
$ lsns  
/grid.service
```

when only the server for the grid example is running and registered with the name server.

## 25.5 dior

JacORB comes with a simple utility to decode an interoperable object reference (IOR) in string form into a more readable representation.

## Usage

```
$ dior [-u] [-c] -i <IOR-string> | -f <filename>
```

- Option `'-u'` Decodes and prints the object key.
- Option `'-c'` Decodes and prints a corbaloc representation of the objectkey.

## Example

In the following example we use it to print out the contents of the IOR that the JacORB name server writes to its file:

```
$ dior -f ~/public.html/NS_Ref
```

```
-----IOR components-----
TypeId      :      IDL:omg.org/CosNaming/NamingContextExt:1.0
Profile Id   :      TAG_INTERNET_IOP
IIOP Version :      1.0
Host        :      160.45.110.41
Port        :      49435
Object key   :      0x52 6F 6F 74 50 4F 41 3A 3A 30 D7 D1 91 E1 70 95 04
```

## 25.6 pingo

“Ping” an object using its stringified IOR. Pingo will call `_non_existent()` on the object’s reference to determine whether the object is alive or not.

### Usage

```
$ pingo -i <IOR-string> | -f <filename>
```

## 25.7 ir

This command starts the JacORB Interface Repository, which is explained in chapter 10.

### Usage

```
$ ir <repository class path> <IOR filename>
```

## 25.8 qir

This command queries the JacORB Interface Repository and prints out re-generated IDL for the repository item denoted by the argument repository ID.

### Usage

```
$ qir <repository Id>
```

## 25.9 ks

This command starts the JacORB KeyStoreManager, which is explained in chapter 13

## Usage

```
$ ks
```

## 25.10 fixior

This command patches host and port information into an IOR file.

## Usage

```
$ fixior <host> <port> <ior.file>
```

# 26 JacORB Threads

Threads that are created and used by JacORB are described below.

## Long-lived threads

### RequestProcessor

The RequestProcessor thread invokes servant code when the thread is assigned a request from the RequestController. This thread invokes firstly the server request interceptors, then the servant manager, and then the servant code. Finally, the RequestProcessor invokes interceptors and servant managers and writes results to the socket when the servant returns the control flow.

The number of RequestProcessor threads which can run is between `jacorb.poa.thread_pool_min` and `jacorb.poa.thread_pool_max` times the number of POAs, or just between those two bounds when `jacorb.poa.thread_pool_shared` is set to “on”. RequestProcessor threads will terminate when the POA is destroyed (in other words when the property is set to “off” and when every POA has it’s own pool of RequestProcessors) or when `ORB.shutdown()` is called, subject to the value of the `jacorb.poa.thread_pool_shared` property.

The RequestProcessor thread is implemented in `org/jacorb/poa/RequestProcessor.java`. Thread instances are pooled in `org/jacorb/poa/RPPoolManager.java`.

### RequestController

The RequestController assigns requests to RequestProcessors and keeps track of active requests, object and POA state. The POA state is checked when the ServerMessageReceptor reads a request from the socket. Request processing can continue if the POA state is active. However, if the POA is inactive or if it is being shut down, then the request is rejected. If the target object is present and not being deactivated, then a RequestProcessor thread is allocated from the pool and the request is handed over to the that thread. One RequestController thread is always provided for each POA: the thread is terminated when the POA is destroyed.

The RequestController thread is implemented in `org/jacorb/poa/RequestController.java`. A reference to the thread is retained by `org/jacorb/poa/POA.java`.

## ServerSocketListener, SSLServerSocketListener

These two threads listen on their respective server sockets and accept new connections. Accepted connections are handed to a thread pool. The `ServerMessageReceptor` uses the thread pool to listen on connections for individual messages.

There can be a maximum of one `ServerSocketListener` and one `SSLServerSocketListener` per ORB, depending on the configuration. These threads will terminate when `ORB.shutdown()` is called.

The `ServerSocketListener` and `SSLServerSocketListener` threads are implemented in the inner classes `Acceptor` and `SSLAcceptor` in `org/jacorb/orb/iiop/IIOPListener.java`: a reference is retained by the class.

## ServerMessageReceptor

`ServerMessageReceptor` threads listen on established connections and read new requests from them. The request's message header is decoded and the POA name is retrieved from the object key after basic checks are made. The request is then handed to the POA for scheduling by the `RequestController`.

The number of `ServerMessageReceptor` threads is between 0 and the value of `jacorb.connection.server.max_receptor_threads`. This upper bound also indicates the maximum number of connections that can be serviced simultaneously. The maximum number of idle threads can be configured using `jacorb.connection.server.max_idle_receptor_threads`.

`ServerMessageReceptor` threads terminate when either `ORB.shutdown()` is called or when the number of idle threads exceeds the maximum specified by `jacorb.connection.server.max_idle_receptor_threads`.

The `ServerMessageReceptor` thread is implemented in `org/jacorb/orb/giop/MessageReceptor.java`: instances are pooled in `org/jacorb/orb/giop/MessageReceptorPool.java`. Both these classes rely on and implement interfaces from JacORB's generic thread pool in `org/jacorb/util/threadpool`.

## ClientMessageReceptor

`ClientMessageReceptor` threads listen on established connections and read new replies received from them. The request's message header is decoded and the reply is handed back to the thread that sent the original request after basic checks are performed. The number of threads which are allowed is between 0 and the value of `jacorb.connection.client.max_receptor_threads`. This upper bound also indicates the maximum number of connections that can be serviced simultaneously. The maximum number of idle threads allowed can be set using `jacorb.connection.client.max_idle_receptor_threads`.

`ClientMessageReceptor` threads terminate when either `ORB.shutdown()` is called or when the number of idle threads exceeds the maximum specified by `jacorb.connection.client.max_idle_receptor_threads`.

This thread is implemented in `org/jacorb/orb/giop/MessageReceptor.java` and its instances are pooled in `org/jacorb/orb/giop/MessageReceptorPool.java`. Both these classes rely on and implement interfaces from JacORB's generic thread pool in `org/jacorb/util/threadpool`.

## BufferManagerReaper

The `BufferManagerReaper` thread ensures that the extra-large buffer cache entry will not live longer than the time specified by `jacorb.bufferManagerMaxFlush`. The `BufferManagerReaper` thread exits when `ORB.shutdown()` is called.

This thread is implemented as inner class `Reaper` in `org/jacorb/orb/BufferManager.java` and a reference is kept by the class.

## AOMRemoval

These threads are used to ensure that calls to `deactivate_object` return immediately. One AOM thread is created per POA. When an object is removed it is placed on a `java.util.concurrent.LinkedBlockingQueue` which this thread processes to finish deactivation of the objects. This thread is a daemon thread and will finish when the POA is destroyed.

## Short-lived threads

### POAChangeToActive

The `POAChangeToActive` thread asynchronously sets the state of those POAs controlled by a `POAManager` to active. A new thread will be created whenever `POAManager.activate()` is called. The thread terminates when all POAs have been activated.

The `POAChangeToActive` thread is implemented as an anonymous inner class in `org/jacorb/poa/POAManager.java`.

### POAChangeToInactive

The `POAChangeToInactive` thread asynchronously sets the state of the POAs controlled by a `POAManager` to inactive. A new thread will be created whenever `POAManager.deactivate()` is called. The thread terminates when all POAs have been deactivated.

The `POAChangeToInactive` thread is implemented as an anonymous inner class in `org/jacorb/poa/POAManager.java`.

## POAChangeToDiscarding

The POAChangeToDiscarding thread asynchronously sets the state of those POAs controlled by a POA-Manager to discarding. A new thread is created whenever `POAManager.discard_requests()` is called. This thread terminates when all POAs have been set to discarding.

The POAChangeToDiscarding thread is implemented as an anonymous inner class in `org/jacorb/poa/POAManager.java`.

## POAChangeToHolding

The POAChangeToHolding thread asynchronously sets the state of those POAs controlled by a POA-Manager to holding. A new thread is created whenever `POAManager.hold_requests()` is called. This thread when all POAs have been set to holding.

The POAChangeToHolding thread is implemented as an anonymous inner class in `org/jacorb/poa/POAManager.java`.

## POADestructor

The POADestructor thread allows asynchronous destruction of a POA. This thread initially synchronizes with the RequestController which waits until all active requests have been finished. Then, all unprocessed requests are discarded by the RequestController thread and destruction of the POA is completed. The thread will then exit.

One POADestructor thread is created whenever `POA.destroy()` is called. Note that destroying a POA will destroy all child POAs. Accordingly, there will be many threads as there are POAs, including child POAs, which are to be destroyed.

The POADestructor thread is implemented as an anonymous inner class in `org/jacorb/poa/POA.java`.

## PassToTransport

The PassToTransport thread is created and performs the network send task whenever a request is sent with the sync scope set to `SYNC_NONE`. The thread exits when it is finished sending and allows the client thread to return immediately.

The PassToTransport thread is implemented as an anonymous inner class in `org/jacorb/orb/Delegate.java`.

## ReplyReceiverTimer

The ReplyReceiverTimer thread manages the termination point for reply timeouts. The thread is created for each anticipated reply when the ReplyEndTime policy is set. The thread exits when the timeout expires



or the anticipated reply is received before timeout expires.

The `ReplyReceiverTimer` thread is implemented as inner class `Timer` in `org/jacorb/orb/ReplyReceiver.java` and a reference is kept by the class.

## SocketConnectorThread

The `SocketConnectorThread` thread connects to the socket for every new connection to the server when `jacorb.connection.client.connect_timeout` is set to a value greater than zero (0). The `SocketConnectorThread` thread provides timeout control which is not available in older JDK versions

The thread exits when either the connection is successfully established or when the timeout expires.

The `ReplyReceiverTimer` thread is implemented as an anonymous inner class in `org/jacorb/orb/ClientIIOPConnection.java`.



# 27 Classpath and Classloaders

This chapter explains some of the problems that may be encountered with classpath and classloaders. It assumes a traditional class loading mechanism has been utilised as opposed to a non-hierarchical or modular mechanism (often deployed within application servers).

Please also refer to [3.2.8](#) which describes JacORB's different methods it uses to load classes and resources.

## 27.1 Running applications

By default JacORB is shipped with runtime scripts to simplify running an application. These scripts use the Java Endorsed Standards Override Mechanism in order to ensure that the JacORB implementation classes and the supplied OMG classes are found in preference to any bundled within the JVM. This mechanism is documented here <http://java.sun.com/j2se/1.5.0/docs/guide/standards> The mechanism utilises the Xbootclasspath to place the classes first.

If this is not used then the Sun OMG classes may be found first. This may cause issues if user code is relying on JacORB's OMG stubs (e.g. if those stubs have a more up to date mapping).

### 27.1.1 ORBSingleton

Unlike an `ORB.init(args,props)` where a developer may pass arguments initialising an `ORBSingleton` with `ORB.init()` does not. This means that unless the developer has either

- Started the JVM supplying `ORBSingletonClass` and `ORBClass` properties
- Overridden System properties prior to calling `ORBInit` with `ORBSingletonClass` and `ORBClass` properties

the OMG ORB class will initialise the wrong `ORBSingleton` **if** endorsed directories are **not** being used. If endorsed directories are being used the JacORB OMG ORB class will automatically load the correct Singleton.

Within JacORB the internal code works around this by utilising a proprietary extension to the OMG stubs. `org.omg.CORBA.ORB` has been modified to extend a new class; `org.omg.CORBA.ORBSingleton`. As this class does not clash with the JDK stubs the internal JacORB code can rely on this to return the correct singleton orb when calling `org.omg.CORBA.ORBSingleton.init()`.

## 27.2 Interaction with Classloaders

The endorsed directory mechanism means that the JacORB classes will be loaded into the bootstrap classloader. If the developer has chosen to instantiate their own child classloader and load the JacORB classes within this (e.g. via `URLClassLoader` downloading the classes over the network) several problems may be encountered:

### Garbage Collection

The Sun JVM will load its OMG ORB classes in preference to those within the child classloader. This means that it will retain a static link to the JacORB `ORBSingleton` implementation within the child classloader. Therefore the classes cannot be fully garbage collected once the classloader is disposed of.

### Class Conflict

As described above the Sun OMG ORB class maintains a static `ORBSingleton` reference. If a second class loader is instantiated, as a `ORBSingleton` already exists in the parent bootclassloader it will not be created. If code checks that `ORB.init () instanceof org.jacorb.orb.ORBSingleton` it will fail. This is because the `ORBSingleton` class created in the first classloader is different to the `ORBSingleton` class created in the second classloader. This behaviour is documented within the Java Language Specification here [http://java.sun.com/docs/books/jls/third\\_edition/html/execution.html#12.1.1](http://java.sun.com/docs/books/jls/third_edition/html/execution.html#12.1.1) and a paper describing the behaviour may be found here <http://www.tedneward.com/files/Papers/JavaStatics/JavaStatics.pdf>

### Solving the Problem

The above problem occurs as `java.net.URLClassLoader` uses the parent-first class-loader delegation model. To solve the issue, the simplest and most effective solution is to use child-first class-loader delegation model. An example of this may be found here <http://www.qos.ch/logging/classloader.jsp>

This model ensures that parent delegation occurs only **after** an unsuccessful attempt to load a class from the child. Therefore the `org.omg.CORBA.*` classes supplied with JacORB would be found and used in preference to the OMG classes supplied by Sun in the bootclassloader. The `ORBSingleton` would be created entirely within the child classloader with no external references. This means the second classloader would also create its own, entirely isolated Singleton class.

# 28 Appendix

## 28.1 API Documentation

The current JacORB core Javadoc is available at <https://jacorb.github.io/JacORB>.

## 28.2 OMG ORB Constants

OMG assigned values used by JacORB are documented [here](#).